



# **NETWORK CAMERA Protocol Spec. HTTP WebView Protocol Specifications**

<b>VB-M40</b>	<b>Firmware Ver. 1.0</b>
<b>VB-M600VE</b>	<b>Firmware Ver. 1.0</b>
<b>VB-M600D</b>	<b>Firmware Ver. 1.0</b>
<b>VB-M700F</b>	<b>Firmware Ver. 1.0</b>

Ver. 2.0

YT1-1618-001

February 28, 2011

CANON INC.

## Change Tracking List

Version	Date	Page	Note
Ver. 1.0	Dec. 15, 2010	-	Version 1.0 was released.
Ver. 2.0	Feb. 28, 2011	29 41, 45, 52  43, 46, 47, 51, 55 51, 52 55  57 - 62 68 - 71 72 - 74 75 - 80  81	3gpp2 of Content-Type was changed to mp4. The term “full auto” was changed to “auto”. The term “flickerfree” was changed to “flickerless”. The term “priority given to shutter speed” was changed to “shutter-priority AE”. The term “shade correction” was changed to “smart shade control”. Notes on c.<c>.dn was corrected/*n was added. “Moving object detection (m)” was deleted from A.4 External Input/Output Information The descriptions of *f in A.6 Intelligent Function Information was corrected. B. VB-M600/VB-M700 information was added. D. JPEG Header information was added. E. H.264 Distribution Function was added. F. HTTP Upload Specification was added. G. Each command and User’s Access Privileges were added.

# Table of Contents

<b>Change Tracking List.....</b>	<b>2</b>
<b>1 Overview.....</b>	<b>5</b>
1.1 Requests and Responses .....	5
1.1.1 Livescope-Status .....	7
1.2 Changes in VB-M40/VB-M600/VB-M700 from Prior Models .....	9
1.3 VB-M40/VB-M600/VB-M700 Model Specific Operations.....	9
1.3.1. Resynchronization Process when Mode Error Occurs .....	9
<b>2 WV-HTTP Specification .....</b>	<b>10</b>
2.1 Functions Provided by the WV-HTTP Protocol .....	10
2.2 Commands and Parameters.....	10
2.3 Session Control Commands.....	12
2.3.1 open.cgi .....	12
2.3.2 close.cgi.....	15
2.3.3 claim.cgi.....	16
2.3.4 yield.cgi.....	18
2.3.5 session.cgi.....	20
2.4 Video Retrieval Commands .....	23
2.4.1 image.cgi .....	23
2.4.2 video.cgi.....	27
2.5 Information Retrieval Commands .....	31
2.5.1 info.cgi .....	31
2.5.2 f.sd=1panorama.cgi.....	38
2.6 Camera Control Commands .....	40
2.6.1 control.cgi .....	40
<b>A VB-M40 Information Retrieval Items.....</b>	<b>49</b>
A.1 System Information .....	49
A.2 Video Information .....	50
A.3 Camera Information.....	50
A.4 External Input/Output Information.....	54
A.5 Preset Information .....	54
A.6 Intelligent Function Information.....	55
A.7 Sound Device Information .....	56
A.8 External Memory Information.....	56
<b>B VB-M600/VB-M700 Information Retrieval Items .....</b>	<b>57</b>
B.1 System Information .....	57
B.2 Video Information .....	58
B.3 Camera Information.....	58
B.5 Preset Information .....	61
B.6 Intelligent Function Information.....	61
B.7 Sound Device Information .....	62
B.8 External Memory Information.....	62

<b>C</b>	<b>Former Model Command.....</b>	<b>63</b>
C.1	Correspondence for Each Type of Information .....	63
<b>D</b>	<b>JPEG Header Information .....</b>	<b>68</b>
JPEG	Area MAP .....	68
JPEG	Image Header (APP0).....	69
Item	Description .....	70
<b>E</b>	<b>H.264 Distribution Function .....</b>	<b>72</b>
E.1	Image Parameters.....	72
About	Image Quality .....	73
E.2	MP4 Fragment.....	73
<b>F</b>	<b>HTTP Upload Specification .....</b>	<b>75</b>
<b>G</b>	<b>Each Command and User Access Privileges .....</b>	<b>81</b>

# 1 Overview

The WebView over HTTP protocol (referred to as “WV-HTTP” hereafter) is a protocol that provides video transmission and camera control functions for network cameras over HTTP. With VB-M40/VB-M600/VB-M700 network cameras, the system of new commands adopted since the VB-C60 network camera is subject to proper operation.

Although commands of former models are supported in VB-M40/VB-M600/VB-M700, proper operation is not guaranteed when using these commands. Therefore, use the commands printed in this specifications.

## 1.1 Requests and Responses

WV-HTTP involves the use of WV-HTTP commands to send video and control the camera. WV-HTTP commands are received as HTTP requests, and video data, camera state information, and so on are sent as HTTP responses. Although the WV-HTTP specifications do not depend on any particular HTTP version, HTTP versions are determined for each individual network camera, and the WV-HTTP client must support the version in question. VB-M40/VB-M600/VB-M700 are HTTP/1.1 compliant.

Since they are HTTP/1.1 compliant, the Host header field is mandatory for HTTP requests. However, contents of the Host header field are ignored. Also, if there is no specification, the permanent connection will be activated. (It will be disconnected if Connection: close is specified.)

Even if WV-HTTP is HTTP/1.1 compliant, pipelines are not supported.

WV-HTTP’s HTTP requests can be issued as HTTP methods, using either GET or POST. The only difference between GET and POST in WV-HTTP is the order in which command parameters are evaluated. The request ring part is evaluated first (GET and POST), followed by the message body part (POST). The client selects whether to use GET or POST.

A request URI starts with “/-wvhttp-01-”, and is comprised of a WV-HTTP command and command parameters. Other than the leading “wvhttp”, the request URI (GET and POST) and message body (POST) are not case-sensitive.

The request formats for GET and POST are shown below.

**Request Format (GET)**

```
GET /-wvhttp-01-/<command>[?<parameter list>_] HTTP/1.1
Host: <host request header field value>
<other HTTP request header_>
<blank line>
```

**Request Format (POST)**

```
POST /-wvhttp-01-/<command>[?<parameter list>_] HTTP/1.1
Host: <host request header field value>
Content-Length: <message body length>
<other HTTP request header_>
<blank line>
<message body (parameter list)>
```

The HTTP request header fields related to WV-HTTP operations are Authorization, Connection, Content-Length, and If-Modified-Since. All other HTTP request header fields are ignored.

The user information of WV-HTTP is extracted from Authorization. Content-Length is required when using the POST method. Also, If-Modified-Since is referenced in panorama-related commands.

The WV-HTTP response format is shown below (the actual content vary according to the WV-HTTP commands). The first line is the HTTP status line, with the HTTP response header field extending from the Date to the blank line, and the WV-HTTP response itself stored in the message body part.

**Response Format**

```
HTTP/1.1 200 OK
Date: <time stamp>
Server: VB
Accept-Ranges: none
Cache — Control: no-cache
Pragma: no-cache
Connection: keep-alive
Keep-Alive: timeout=10
Livescope-Status: 0
Content-Length: <message body length>
Content-Type: <message body mime-type>
<blank line>
<message body>
```

Livescope-Status is an independent extended field that shows the result of executing the WV-HTTP command. When returning the WV-HTTP response, 200 OK is returned as the HTTP status (including Livescope-Status). When WV-HTTP response is not returned, another HTTP status may be returned. The main status possibilities are shown below.

**Table 1-1 HTTP Status**

HTTP Status	Meaning
304 Not Modified	Data was not updated (panorama image, etc.).
400 Bad Request	A host header field was not specified (HTTP/1.1).
401 Unauthorized	User access restrictions were violated.
403 Forbidden	Host access restrictions were violated.
404 Not Found	No resource exists that supports this request URI.
411 Length Required	Content-Length was not specified (POST method).
500 Internal Server Error	The request was refused due to an internal processing error.
503 Service Unavailable	The request was refused due to temporary overload or memory shortage.

### 1.1.1 Livescope-Status

The value of the Livescope-Status header field is “0” when the WV-HTTP command is processed normally. One of the following error codes/error messages is returned when an error occurs:

**Table 1-2 Livescope- Status**

Livescope-Status	Meaning
0	Processed normally.
301 No Camera Control Right	The request was refused because no control privilege request was issued.
302 Camera is not available	A camera that does not exist was specified in the camera_id parameter.
303 Camera is not controllable	An anomaly in the camera part has caused it to enter an uncontrollable state.
401 Unknown Operator	An undefined command was specified.
403 Invalid Parameter Value	An invalid parameter value was specified.
404 Operation Timeout	The command did not finish executing within the response timeout period.
406 Parameter Missing	A mandatory parameter was not specified.
407 Invalid Request	An invalidated session function was requested.
408 Conflict	An exclusive operation was requested.
409 Conflict	A recording stream was requested during image evacuation to external memory.
501 Unknown Connection ID	The specified session does not exist.
503 Too many clients	The maximum number of connections was exceeded.
507 Insufficient Privilege	Cannot access due to access time period restrictions, etc.
508 Request Refused	The request was rejected due to temporary connection limitations of the camera.

WV-HTTP error responses appear as follows overall. The message body's Content-Type is always text/plain; charset=utf-8.

**WV-HTTP Error Response Format**

HTTP/1.1 200 OK

<HTTP response header field>

Livescope-Status: <error code> <error message>

Content-Length: <message body length>

Content-Type: **text/plain; charset=utf-8**

--- WebView Livescope Http Server Error ---

<error message>

<additional error information>



## **1.2 Changes in VB-M40/VB-M600/VB-M700 from Prior Models**

WV-HTTP of VB-M40/VB-M600/VB-M700 is basically forward compatible with new command systems of VB-C60, except the following changes. The details are described in the chapters of each command and parameter.

- Modification of interpretations of some parameters
- Change the ServerResponses header field to VB
- Additional commands of new functions
- Addition/modification of parameters due to differences in camera functions

## **1.3 VB-M40/VB-M600/VB-M700 Model Specific Operations**

### **1.3.1. Resynchronization Process when Mode Error Occurs**

When a mode error occurs during control.cgi process, a response "<Item Name>==?" is returned. However, there are specific conditions where mode responses cannot be returned, and in these cases, the camera status will be resynchronized and the result is notified as an event (info.cgi).

Corresponding conditions are as follows.

- When white balance is modified with control.cgi during day-night switching of auto day-night
- When white balance is modified with commands (commands other than control.cgi) without definition of the mode error response

## 2 WV-HTTP Specification

### 2.1 Functions Provided by the WV-HTTP Protocol

WV-HTTP provides the following functions:

- Starting and ending sessions
- Acquiring video data
- Camera control
- Camera control privileges
- Event processing
- Acquiring various types of information

### 2.2 Commands and Parameters

WV-HTTP commands are comprised from a command name and parameters.

Parameters are given in the format “<name>=<value>”, and are specified in the request URI's query string with ‘&’ as a delimiter (or delimited with carriage returns inside the message body).

Example: `http://192.168.100.1/-wvhttp-01-/image.cgi?pan=1000&tilt=1000`

Parameters specified in the query string must be URL-encoded. Although there are no restrictions in the order of specification for parameters, if the same parameter is specified multiple times, excluding parameters that can be specified several times, then the last parameter will be used.

Each command parameter and response will be described below. Depending on the parameter, it may be possible to partially omit names or values. In this case, the part that can be omitted will be shown as “[...]”.

The majority of parameters may be omitted in WV-HTTP, but those that cannot be omitted are shown as “(mandatory)”.

When using WV-HTTP commands, after receiving a response to the sent command, the next command must be sent. This is to ensure the order of sent commands, and if the next command is sent before waiting for a response to the command, the order of command processing cannot be ensured and may result in an unexpected operation.

WV-HTTP provides the following commands:

Starting and ending sessions:	open.cgi, close.cgi, session.cgi
Acquiring video data:	image.cgi, video.cgi
Camera control/ External device operations:	control.cgi
Camera control privileges:	claim.cgi, yield.cgi
Acquiring various types of information:	info.cgi

control.cgi and info.cgi can be used sessionless. When control privileges are controlled using claim.cgi and yield.cgi, a session must be started using open.cgi.

## 2.3 Session Control Commands

### 2.3.1 open.cgi

#### Format

`http://<ipaddress>/-wvhttp-01-/open.cgi?[s.priority=value&v=value]`

#### Function Overview

This function creates a WV-HTTP session.

When creating a privileged session, specify the priority with “priority”. This priority level is used for access management, control privileges management, and so on. Session life spans differ depending on the priority, with privileged sessions (those with a priority of 5 or higher) unlimited, and general sessions (those with a priority of 0) limited to the maximum connection time (the set value).

‘v’ parameter can be used to specify the video stream type for a session to be used for acquiring video. The specified value is used as the default video stream for video retrieval commands (image.cgi, video.cgi). The values which can be specified depend on the model and settings (info.cgi). It can be changed after the session is created, or after the video transmission starts (refer to session.cgi).

If a session is successfully created, then the session identifier, remaining time, and priority are returned as the response. For sessions with video transmission functions, the video stream information is also added to the response.

If the maximum connections limit is exceeded, a session will not be created and a 503 error is returned to Livescope-Status.

Also, the session will not be created and a 507 error response is returned to Livescope-Status if the access time period or some other connection restriction prevents the connection.

## Parameters

[s.]priority	<p>Priority level (0: general user, 5 to 50: operator). Value defaults to 0 when omitted. Priority levels of users other than general users are restricted to the user, and priority levels between 1 and 4 are treated as 5 (1 to 4 are a reserved range).</p>
v	<p>Used to specify the video stream. Specify with the format &lt;T&gt;[:&lt;W&gt;[x&lt;H&gt;[:&lt;R&gt;]]]]. &lt;T&gt; is the type (jpg or h264). &lt;W&gt; and &lt;H&gt; are the image size (the width and height in pixel units). &lt;R&gt; is the frame rate (the number of frames per 1,000 seconds). (example: jpg:640 x 480::30000)</p> <ul style="list-style-type: none"> <li>• If there is no match for a specified value, then the closest thing to the specified value (as long as the value is above the specified value, yet does not exceed the maximum value for the device) will be selected.</li> <li>• When h264 is specified in &lt;T&gt;, &lt;W&gt;, &lt;H&gt; or &lt;R&gt; cannot be specified. (Setting values of the device will be used)</li> <li>• When &lt;WxH&gt; is not specified, default values of the device will be used.</li> <li>• When v=null is specified, a session without a video delivery function will be created. If a command related to video delivery is requested of this session created by specifying null, then a 407 error is returned to Livescope-Status.</li> </ul>

For operators (non-administrators) to create a privileged session, privileged camera control must be permitted depending on the settings. When privileged camera control is prohibited, non-administrator's privileged session will be deleted at that point, and new sessions will not be able to be created.

## Responses

Content-Type	text/plain; charset=utf-8
Extended header	Livescope-Status: status code
Message body	s:=<session identifier> s.origin:=<camera address>:<HTTP port> s.duration:=<time remaining in the session> s.priority:=<session priority level > v:=<video stream>
Notes	s.duration is the remaining time in seconds (0 means no limit). v is only specified when the video stream is valid (when v is not null).

## Error

Livescope-Status	Error details
407 Invalid Request	An invalidated session function was requested.
503 Too many clients	Maximum connections limit exceeded.
507 Insufficient Privilege	Access time period or some other connection restriction prevents the connection.

## Example of Parameters and Responses

GET /-vvhttp-01-/open.cgi HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: 95

Server: VB

s:=8a96-c09b18f0

s.origin:=192.168.100.1:80

s.duration:=0

s.priority:=0

v:=jpg:320x240:3:30000

### 2.3.2 close.cgi

#### Format

`http://<ipaddress>/-wvhttp-01-/close.cgi?s=<session-id>`

#### Function Overview

This function deletes the WV-HTTP session.

#### Parameters

s (mandatory)	Specify the session identifier. <b>s=&lt;session id&gt;</b>
---------------	--

#### Responses

Content-Type	text/plain; charset=utf-8
Extended header	Livescope-Status: status code
Message body	OK.

#### Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
501 Unknown Connection ID	Specified session does not exist.

#### Example of Parameters and Responses

`GET /-wvhttp-01-/close.cgi?s=8a96-c09b18f0 HTTP/1.1`

⇒

`HTTP/1.1 200 OK`

...

`Livescope-Status: 0`

`Content-Length: 4`

`Server: VB`

`OK.`

### 2.3.3 claim.cgi

#### Format

http://<ipaddress>/-wvhttp-01-/claim.cgi?s=<session-id>

#### Function Overview

This function requests camera control privileges.

The control privilege allocation time is determined by the session's priority level, with privileged sessions unlimited, and others set to a finite value (the set value).

Operator level sessions can secure the control privilege even when another session with the same priority level has already secured the control privilege. The session forfeiting the control privilege will be informed with an event.

#### Parameters

s (mandatory)	Specify the session identifier. <b>s=&lt;session id&gt;</b>
---------------	--

#### Responses

(If the State of Control Privileges Has Changed)					
Content-Type	text/plain; charset=utf-8				
Extended header	Livescope-Status: status code				
Message body	s.control:=<state of camera control privileges>				
Notes	<div><div>The camera control privileges can be in one of the following two states. If the allocated time and waiting time are both limited, then the time will be appended after the ':' in millisecond units.</div><table><tr><td>Control right successfully secured</td><td>enabled[:&lt;allocated time&gt;]</td></tr><tr><td>Waiting to secure control privilege</td><td>waiting[:&lt;waiting time&gt;]</td></tr></table><div>The results are notified as an event as well (2.5.1 info.cgi).</div></div>	Control right successfully secured	enabled[:<allocated time>]	Waiting to secure control privilege	waiting[:<waiting time>]
Control right successfully secured	enabled[:<allocated time>]				
Waiting to secure control privilege	waiting[:<waiting time>]				



(If the State of Control Privileges Has Not Changed)

Content-Type	text/plain; charset=utf-8	
Extended header	Livescope-Status: status code	
Message body	s.control==<state of camera control privileges>	
Notes	The camera control privileges can be in one of the following three states. The allocated time and waiting time are the same as above.	
	While control privilege is secured	enabled[:<allocated time>]
	While waiting for control privilege	waiting[:<waiting time>]
	Failed to secure control privilege	disabled

## Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
501 Unknown Connection ID	Specified session does not exist.

## Example of Parameters and Responses

GET /-wvhttp-01-/claim.cgi?s=8a96-c09b18f0 HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: 25

Server: VB

s.control:=enabled:20000

## 2.3.4 yield.cgi

### Format

`http://<ipaddress>/-wvhttp-01-/yield.cgi?s=<session-id>`

### Function Overview

This function releases camera control privileges, or cancels the state of waiting for camera control privileges.

### Parameters

s (mandatory)	Specify the session identifier. <b>s=&lt;session id&gt;</b>
---------------	--

### Responses

(If the State of Control Privileges Has Changed)

Content-Type	text/plain; charset=utf-8
Extended header	Livescope-Status: status code
Message body	s.control:=disabled
Notes	The results are notified as an event as well (2.5.1 info.cgi).

(If the State of Control Privileges Has Not Changed)

Content-Type	text/plain; charset=utf-8
Extended header	Livescope-Status: status code
Message body	s.control==disabled

### Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
501 Unknown Connection ID	Specified session does not exist.

### **Example of Parameters and Responses**

GET /-wvhttp-01-/yield.cgi?s=8a96-c09b18f0 HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: 20

Server: VB

s.control:=disabled

### 2.3.5 session.cgi

#### Format

http://<ipaddress>/-vvhttp-01-/session.cgi?s=<session-id>[&v=value]

#### Function Overview

This function retrieves or changes session-specific attributes.

2 types of session-specific attributes are currently supported, priority level and video stream.

The session's priority level is used in access management and control privilege management. When the priority level is changed, particularly when low priority level is set, the following operations may occur:

##### Session deletion (disconnection)

When access is prohibited due to the setting, the session will be forcefully deleted.

##### Camera control privilege forfeit

The state of the control privilege queue will change, and the control privilege may be forfeited or the waiting time may be lengthened. When a priority level for which camera control is prohibited is set, the control privilege will be forfeited.

## Parameters

s (mandatory)	Specify the session identifier. <b>s=&lt;session id&gt;</b>										
[s.]priority	Priority level (0: general user, 5 to 50: operator). Value defaults to 0 when omitted. Priority levels of users other than general users are restricted to the user, and priority levels between 1 and 4 are treated as 5 (1 to 4 are a reserved range).										
v	<p>Used to specify the video stream. Specify with the format &lt;T&gt;[:&lt;W&gt;[x&lt;H&gt;[:&lt;R&gt;]]]. &lt;T&gt; is the type (jpg or h264). &lt;W&gt; and &lt;H&gt; are the image size (the width and height in pixel units). &lt;R&gt; is the frame rate (the number of frames per 1,000 seconds). (example: jpg:640 x 480::30000)</p> <ul style="list-style-type: none"> <li>If there is no match for a specified value, then the closest thing to the specified value (as long as the value is above the specified value, yet does not exceed the maximum value for the device) will be selected.</li> <li>When h264 is specified in &lt;T&gt;, &lt;W&gt;, &lt;H&gt; or &lt;R&gt; cannot be specified. (Setting values of the device will be used)</li> <li>When &lt;WxH&gt; is not specified, default values of the device will be used.</li> </ul> <p>When the Video Retrieval Commands (2.4.1 image.cgi, 0 video.cgi) is being processed, the type cannot be changed and 408 error is returned to Livescope=Status.</p> <p><b>Error</b></p> <table border="1"> <thead> <tr> <th>Livescope-Status</th><th>Error details</th></tr> </thead> <tbody> <tr> <td>401 Unknown Operator</td><td>An undefined command was specified. Required parameter is not specified</td></tr> <tr> <td>403 Invalid Parameter Value</td><td>An invalid parameter value was specified</td></tr> <tr> <td>408 Conflict</td><td>An exclusive operation was requested</td></tr> <tr> <td>501 Unknown Connection ID</td><td>Specified session does not exist</td></tr> </tbody> </table>	Livescope-Status	Error details	401 Unknown Operator	An undefined command was specified. Required parameter is not specified	403 Invalid Parameter Value	An invalid parameter value was specified	408 Conflict	An exclusive operation was requested	501 Unknown Connection ID	Specified session does not exist
Livescope-Status	Error details										
401 Unknown Operator	An undefined command was specified. Required parameter is not specified										
403 Invalid Parameter Value	An invalid parameter value was specified										
408 Conflict	An exclusive operation was requested										
501 Unknown Connection ID	Specified session does not exist										
	<p><b>Example of Parameters and Responses</b></p> <pre>GET /-wvhttp-01-/image.cgi?v=jpg:320x240 HTTP/1.1 ⇒ HTTP/1.1 200 OK ... Livescope-Status: 0 Content-Length: xxxxx Server: VB  {JPEG image data of 320 x 240}</pre>										

## Responses

Content-Type	text/plain; charset=utf-8
Extended header	Livescope-Status: status code
Message body	s.priority:=<new priority level> v:=<new video stream>
Notes	The details of a changed item will be notified as an event as well (2.5.1 info.cgi). The response will be as follows for an item that is not changed, and no event notification will occur: s.priority==<current priority level> v==<current video stream>

## Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
501 Unknown Connection ID	Specified session does not exist.

## Example of Parameters and Responses

GET /-vvhttp-01-/session.cgi?s=8a96-c09b18f0 HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: 37

Server: VB

s.priority==0

v== jpg:320:1:30000

## 2.4 Video Retrieval Commands

### 2.4.1 image.cgi

#### Format

`http://<ipaddress>/-wvhttp-01-/image.cgi?[s=<session-id>[&v=value][&c.zoom=value][&c.pan=value][&c.tilt=value][&cache]`

#### Function Overview

This function requests a JPEG still image.

Operations differ as follows, depending on whether a session identifier <s> is specified or a session identifier is not specified:

When the session identifier <s> is specified:

Camera control parameters of c.pan/c.tilt/c.zoom are ignored.

Video stream setting of sessions specified by the session identifier is used.

Video stream setting can be set or changed by using open.cgi or session.cgi.

If the video type of a video stream setting for a specified session is H.264, the video type of a video stream setting for a specified session will be changed to JPEG and an event notification is executed by info.cgi. Even after image.cgi command processing is finished, video stream setting of the session will stay as JPEG.

During the transmission of a video stream (running video.cgi command), this command will not be able to be used. If this command is requested during the transmission of a video stream, 408 error is returned to Livescope-Status.

When the session identifier <s> is not specified:

A video type will be selected based on the video stream specifier <v>.

Although camera control parameters can be used to specify the shooting position, when control privilege cannot be acquired for reasons such as a client with higher priority is connected, camera will not be controlled.

Image types other than jpg cannot be specified for the video stream specifier <v>. If types other than Jpg are specified, 403 error is returned to Livescope-Status.

Although it is up to the application to decide how to differentiate when using these, the method for specifying the session identifier is suited for use in displaying a pseudo video by repeatedly sending JPEG still images. To retrieve a single JPEG still image, use of image.cgi that does not specify a session identifier is convenient.

When this command is issued multiple times simultaneously, within the same session, commands will be processed based on the order in which it is received. Although the same JPEG still image data will not be sent multiple times, since there is no guarantee that the order of sending and the order of receiving will be the same, the client side must sort by serial number.

## Parameters

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>									
v	<p>Used to specify the video stream. Specify with the format &lt;T&gt;[:&lt;W&gt;[x&lt;H&gt;]]. &lt;T&gt; is the type (jpg or h264). &lt;W&gt; and &lt;H&gt; are the image size (the width and height in pixel units). (example: jpg:640 x 480)</p> <ul style="list-style-type: none"><li>• If there is no match for a specified value, then the closest thing to the specified value (as long as the value is above the specified value, yet does not exceed the maximum value for the device) will be selected.</li><li>• When h264 is specified in &lt;T&gt;, &lt;W&gt; or &lt;H&gt; cannot be specified. (Setting values of the device will be used)</li><li>• WxX can be left blank, in which case size set in “Video Size:Video Transmission” will be used.</li></ul>									
[c.<c>.]zoom	<table><tr><td colspan="2">Specify the zoom position or operation.</td></tr><tr><td>&lt;position&gt;</td><td>Moves to &lt;position&gt; (the horizontal angle of view in 0.01 degree units).</td></tr><tr><td>d[±]&lt;difference&gt;</td><td>Moves to a position that is the current position ±&lt;difference&gt;.</td></tr><tr><td>v[+]&lt;magnification ratio&gt;</td><td>Moves to the &lt;magnification ratio&gt; position based on the current angle of view. The &lt;magnification ratio&gt; is a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.</td></tr></table>		Specify the zoom position or operation.		<position>	Moves to <position> (the horizontal angle of view in 0.01 degree units).	d[±]<difference>	Moves to a position that is the current position ±<difference>.	v[+]<magnification ratio>	Moves to the <magnification ratio> position based on the current angle of view. The <magnification ratio> is a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.
Specify the zoom position or operation.										
<position>	Moves to <position> (the horizontal angle of view in 0.01 degree units).									
d[±]<difference>	Moves to a position that is the current position ±<difference>.									
v[+]<magnification ratio>	Moves to the <magnification ratio> position based on the current angle of view. The <magnification ratio> is a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.									



[c.<c>].pan	Specify the pan position.	
	<position>	Moves to <position> (in 0.01 degree units, with the right side positive).
	d[±]<difference>	Moves to a position that is the current position ±<difference>.
	V[±]<difference>	Moves to a position that is the current position ±<difference>. The difference is a relative position based on the screen, with 0 representing the center, -100 representing the left edge, and 100 representing the right edge.
[c.<c>].tilt	Specify the tilt position.	
	<position>	Moves to <position> (in 0.01 degree units, with the up side positive).
	d[±]<difference>	Moves to a position that is the current position ±<difference>.
	v[±]<difference>	Moves to a position that is the current position ±<difference>. The difference is a relative position based on the screen, with 0 representing the center, -100 representing the bottom edge, and 100 representing the top edge.
cache	Specify the HTTP cache to on (or 1), or off (or 0). Value defaults to 0 when omitted. When on (or 1) is specified, the response header does not include Cache-Control, etc., and acquired image is subject to caching for browsers, etc.	

## Responses

Content-Type	image/jpeg
Extended header	Livescope-Frame-Number: <JPEG data serial number>
	Livescope-Status: status code
Message body	<JPEG data>
Notes	The extended header is only used when a session identifier is specified.

## Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
403 Invalid Parameter Value	An invalid parameter value was specified.
408 Conflict	An exclusive operation was requested.
501 Unknown Connection ID	Specified session does not exist.

### Example of Parameters and Responses

GET /-vvhttp-01-/image.cgi?v=jpg:320x240 HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: xxxxx

Server: VB

{JPEG image data with a resolution of 320 x 240}

## 2.4.2 video.cgi

### Format

`http://<ipaddress>/-wvhttp-01-/video.cgi?[s=<session-id>[&v=value] [&duration=value] [&type=value]`

### Function Overview

This function requests transmission of the video stream. Operations differ as follows, depending on whether or not a session identifier is specified:

When the session identifier is specified:

The session's video stream setting is used (initialize with open.cgi, change with session.cgi).

This command is prohibited during the transmission of a video stream or a JPEG still image (image.cgi). When this command is requested during transmission of a JPEG still image (image.cgi), 408 error is returned to Livescope-Status.

Transmission process of the video stream by video.cgi will continue until either the session ends or the client cuts the connection.

When the session identifier is not specified:

Selection will be made based on the video stream specifier <v>. The transmission process will continue until either the period specified by duration comes to an end, or the client cuts the connection.

For video stream by video.cgi, the transmission control method (buffering policy) can be specified by <type>. The transmission control method and the session identifier specification are unrelated to each other.

## Parameters

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>				
v	Used to specify the video stream. Specify with the format V=<T>[:<W>[x<H>[:<R>]]] <T> is the type (jpg or h264). <W> and <H> are the image size (the width and height in pixel units). <R> is the frame rate (the number of frames per 1,000 seconds). (example: jpg:640 x 480::30000) <ul style="list-style-type: none"> <li>If there is no match for a specified value, then the closest thing to the specified value (as long as the value is above the specified value, yet does not exceed the maximum value for the device) will be selected.</li> <li>When h264 is specified in &lt;T&gt;, &lt;W&gt;, &lt;H&gt; or &lt;R&gt; cannot be specified. (Setting values of the device will be used)</li> </ul> WxH and Q can be left blank, in which case the device's default values will be used.				
duration	Specify the video transmission time (in seconds). duration=<value> 0 (the default setting) means there is no limit In the case of general users, the limit is the maximum connection time setting for the device. The maximum connection time setting does not apply to users with privilege or more. User information is acquired from the HTTP Authorization header.				
type	Specifies the transmission control method (buffering policy). type=<live   rec> Specify either live (live) or rec (record). When parameter other than Rec is selected, it is treated as live. <table border="1" data-bbox="662 1294 1353 1482"> <tr> <td>live</td><td>This control setting discards image data as it is collected, in order to send the newest image data possible.</td></tr> <tr> <td>rec</td><td>This control setting buffers image data as it is collected, in order to prevent the loss of data to the extent possible.</td></tr> </table> <p>Since the buffer capacity is limited, when the buffer fills, data may be lost, even if rec is specified. If the video stream format is h264, or transmission frame rate exceeds 10 fps, then type=rec cannot be specified and 407 error is returned to Livescope-Status. Only a single connection can specify type=rec with video.cgi. When multiple video.cgi commands simultaneously specify type=rec, 408 error is returned to Livescope-Status.</p>	live	This control setting discards image data as it is collected, in order to send the newest image data possible.	rec	This control setting buffers image data as it is collected, in order to prevent the loss of data to the extent possible.
live	This control setting discards image data as it is collected, in order to send the newest image data possible.				
rec	This control setting buffers image data as it is collected, in order to prevent the loss of data to the extent possible.				

### Responses (When the Stream Type Is jpg)

Content-Type	multipart/x-mixed-replace;boundary=boundary
Extended header	Livescope-Status: status code
Message body	--boundary Content-Type: image/jpeg Content-Length: <1 <sup>st</sup> JPEG data size>  <1 <sup>st</sup> JPEG data> --boundary Content-Type: image/jpeg Content-Length: <2 <sup>nd</sup> JPEG data size>  <2 <sup>nd</sup> JPEG data> ... --boundary Content-Type: image/jpeg Content-Length: <last JPEG data size>  <last JPEG data> --boundary--

### Responses (When the Stream Type Is h264)

Content-Type	video/mp4
Extended header	Livescope-Status: status code
Message body	The MPEG-4 data in MP4 fragment format.

### Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
408 Conflict	An exclusive operation was requested.
501 Unknown Connection ID	Specified session does not exist.

### Example of Parameters and Responses

GET /-vvhttp-01-/video.cgi?v=jpg:320x240::10000 HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Content-Type: image/jpeg

Livescope-Status: 0

Connection: close

Server: VB

--boundary

Content-Type: image/jpeg

Content-Length: ...

{JPEG image data with a resolution of 320 x 240 and an image quality of 3, at 10 fps}

--boundary

Content-Type: image/jpeg

Content-Length: xxxxxx

{JPEG image data}

...

## 2.5 Information Retrieval Commands

### 2.5.1 info.cgi

#### Format

```
http://<ipaddress>/-wvhttp-01-/info.cgi?[s=<session-id>][&type=value][&timeout=value]
```

#### Function Overview

This function retrieves various types of information (refer to Appendix A).

Operations differ as follows, depending on whether or not session identifier <s> is specified:

When the session identifier is specified:

All specified information is returned the first time, and differential information not yet retrieved is returned the second and subsequent times.

Although any existing differential information which has not yet been retrieved will be returned immediately as a response, the command will wait until a change happens if differential information not yet received does not exist.

When the session identifier is not specified:

All specified information is returned immediately.

There are 2 response format types, "item name:=value" or "item name ==value".

Item name:=value:

All specified items at the first time, or items changed by an external factor (controlled by another client, a setting change, etc.)

Item name==value:

An item changed by a command transmitted within the same session

However, the command response "item name:=value" is returned.

When the session identifier is not specified, "item name:=value" will always be returned.

When the type parameter is used, the changed part can be retrieved in stream format (type=stream). In this case, the operation is as described above the first time, depending on whether or not there is a session identifier specification, and the differential is sent if a change happens from the second time on.

When the timeout parameter is used, it is possible to specify a time limit for the response. If the information that is to be notified does not occur during the prescribed time, then the response will execute with only a timestamp line.

It is not possible to simultaneously execute multiple event retrieval commands within the same session. If multiple event commands are requested within the same session, 408 error is returned to Livescope-Status.

## Parameters

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>				
item	<p>This specifies the item with information to be retrieved. The item name is hierarchical, and is specified in the following format:</p> <table border="1"> <tr> <td>c</td><td>Everything in c and under is included in the acquisition target.</td></tr> <tr> <td>c!</td><td>Everything in c and under is excluded from the acquisition target.</td></tr> </table> <p>It is also possible to list items with item=s,c... (or item=s&amp;item=c...), and in that case, the item specifications are evaluated in the order of specification). If there is no item specification, then this is processed as if all items were specified.</p>	c	Everything in c and under is included in the acquisition target.	c!	Everything in c and under is excluded from the acquisition target.
c	Everything in c and under is included in the acquisition target.				
c!	Everything in c and under is excluded from the acquisition target.				
type	When stream is specified, the differential is notified in stream format.				
timeout	<p>This is the time limit for a response (in seconds). The upper and lower limit values are dependent on implementation.</p> <p>If no event occurs before the timeout period ends, then only the timestamp line will be sent. When there is no timeout specification, a timeout will still occur if there is no event within the prescribed time period.</p>				
Notes	When the item parameter is used, it is recommended to specify the same item throughout the session. Even if the item is changed during a session, this will not result in an error, but note that a mismatch may result in the order of updating and the order of retrieval.				

## Responses (Normal)

Content-Type	text/plain; charset=utf-8
Message body	timestamp=<time stamp(seconds.milliseconds)> realtime=<real time(seconds.milliseconds)> <specified information or differential information>
Notes	<p>The timestamp is a time specific to the network camera (the amount of time that has passed since startup).</p> <p>The realtime is real time of the network camera.</p>



### Responses (Stream Format)

Content-Type	multipart/x-mixed-replace;boundary=boundary
Message body	--boundary Content-Type: text/plain; charset=utf-8 Content-Length: <data length>  timestamp=<time stamp(seconds.milliseconds)> realtime=<real time(seconds.milliseconds)> <specified information or differential information> --boundary Content-Type: text/plain; charset=utf-8 Content-Length: <data length>  timestamp=<time stamp(seconds.milliseconds)> realtime=<real time(seconds.milliseconds)> <differential information> --boundary ... --boundary Content-Type: text/plain; charset=utf-8 Content-Length: <data length>  timestamp=<time stamp(seconds.milliseconds)> realtime=<real time(seconds.milliseconds)> --boundary--
Notes	The timestamp line is sent alone the final time.

### Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
408 Conflict	An exclusive operation was requested.
501 Unknown Connection ID	Specified session does not exist.

## Example of Parameters and Responses

GET /-vvhttp-01-/info.cgi HTTP/1.1  
⇒  
HTTP/1.1 200 OK  
...  
Content-Type: text/plain; charset=utf-8  
Livescope-Status: 0  
Content-Length: 3092  
Server: VB

timestamp=442076.322  
realtime=1288107713.428  
s.epoch:=Thu, 21 Oct 2010 12:54:13 +0900  
s.hardware:=Canon VB-M40  
s.firmware:=1.0.0  
s.protocol:=02.00  
v.list:=jpg:160x120:3:30000,jpg:320x240:3:30000,jpg:640x480:3:30000,jpg:1280x960:3:30000,h264:640x480:0:30000  
v.h264.cbr:=2048  
c:=1  
c.count:=1  
c.l.type:=Canon VB-M40  
c.l.status:=enabled  
c.l.name.asc:=Camera  
c.l.name.utf8:=  
c.l.exp:=auto  
c.l.exp.list:=auto,flickerfree,tv>manual  
c.l.ae.autoss:=30  
c.l.ae.autoss.list:=8,15,30  
c.l.ae.shutter.list:=8,15,30,60,100,120,250,500,1000,2000,4000,8000  
c.l.ae.brightness:=0  
c.l.ae.brightness.min:=-8  
c.l.ae.brightness.max:=8  
c.l.ae.brightness.list:=-6,-4,-2,0,2,4,6  
c.l.ae.photometry:=center  
c.l.ae.photometry.list:=center,average,spot  
c.l.me.shutter.list:=1,2,4,8,15,30,60,100,120,250,500,1000,2000,4000,8000  
c.l.me.iris.min:=5  
c.l.me.iris.max:=32  
c.l.me.gain.min:=0  
c.l.me.gain.max:=40  
c.l.dn:=off  
c.l.dn.mode:=manual  
c.l.dn.mode.list:=manual,auto1  
c.l.wb:=auto  
c.l.wb.list:=auto>manual,one\_shot,sodium,halogen,mercury,fluorescent\_w,fluorescent\_l,fluorescent\_h  
c.l.is:=off  
c.l.nr:=1  
c.l.nr.min:=0

c.1.nr.max:=2  
c.1.ac:=1  
c.1.ac.min:=0  
c.1.ac.max:=2  
c.1.shade:=off  
c.1.shade.param:=0  
c.1.shade.param.min:=0  
c.1.shade.param.max:=6  
c.1.focus:=auto  
c.1.focus.list:=auto,infinity>manual  
c.1.zoom:=1147  
c.1.zoom.d:=280  
c.1.zoom.min:=280  
c.1.zoom.max:=5540  
c.1.zoom.limit.min:=280  
c.1.zoom.limit.max:=5540  
c.1.zoom.speed.min:=0  
c.1.zoom.speed.max:=7  
c.1.pan:=10525  
c.1.pan.min:=-17000  
c.1.pan.max:=17000  
c.1.pan.limit.min:=-17000  
c.1.pan.limit.max:=17000  
c.1.pan.speed.min:=62  
c.1.pan.speed.max:=15000  
c.1.tilt:=-350  
c.1.tilt.min:=-9000  
c.1.tilt.max:=1000  
c.1.tilt.limit.min:=-9000  
c.1.tilt.limit.max:=1000  
c.1.tilt.speed.min:=62  
c.1.tilt.speed.max:=15000  
c.1.view:=-19770:3078:39540:14156  
c.1.view.restriction:=off  
c.1.panorama.count:=0  
i.count:=2  
i.1:=0  
i.1.name.asc:=  
i.1.name.utf8:=  
i.2:=0  
i.2.name.asc:=  
i.2.name.utf8:=  
o.count:=2  
o.1:=0  
o.1.name.asc:=  
o.1.name.utf8:=  
o.2:=0  
o.2.name.asc:=  
o.2.name.utf8:=  
p.count:=1  
p.1.name.asc:=p1

p.1.name.utf8:=プリセット 1  
p.1.name.lang:=ja  
p.1.c:=1  
p.1.pan:=10525  
p.1.tilt:=-350  
p.1.zoom:=1167  
p.1.focus:=auto  
p.1.ae.brightness:=0  
p.1.shade:=off  
p.1.shade.param:=0  
p.1.wb:=auto  
r.engine:=1  
r.meta:=off  
r.pseudo:=0  
r.count:=15  
r.1:=0  
r.1.name.asc:=  
r.1.name.utf8:=  
r.1.type:=0  
r.2:=0  
r.2.name.asc:=  
r.2.name.utf8:=  
r.2.type:=0  
r.3:=0  
r.3.name.asc:=  
r.3.name.utf8:=  
r.3.type:=0  
r.4:=0  
r.4.name.asc:=  
r.4.name.utf8:=  
r.4.type:=0  
r.5:=0  
r.5.name.asc:=  
r.5.name.utf8:=  
r.5.type:=0  
r.6:=0  
r.6.name.asc:=  
r.6.name.utf8:=  
r.6.type:=0  
r.7:=0  
r.7.name.asc:=  
r.7.name.utf8:=  
r.7.type:=0  
r.8:=0  
r.8.name.asc:=  
r.8.name.utf8:=  
r.8.type:=0  
r.9:=0  
r.9.name.asc:=  
r.9.name.utf8:=  
r.9.type:=0

```
r.10:=0
r.10.name.asc:=
r.10.name.utf8:=
r.10.type:=0
r.11:=0
r.11.name.asc:=
r.11.name.utf8:=
r.11.type:=0
r.12:=0
r.12.name.asc:=
r.12.name.utf8:=
r.12.type:=0
r.13:=0
r.13.name.asc:=
r.13.name.utf8:=
r.13.type:=0
r.14:=0
r.14.name.asc:=
r.14.name.utf8:=
r.14.type:=0
r.15:=0
r.15.name.asc:=
r.15.name.utf8:=
r.15.type:=0
a.count:=1
a.1.send:=on
a.1.recv:=on
a.1.detect:=0
```

## 2.5.2 f.sd:=1panorama.cgi

### Format

`http://<ipaddress>/-wvhttp-01-/panorama.cgi?[s=<session-id>]`

### Function Overview

This function retrieves panorama image data.

If there is no session specification, then this is limited to administrators.

If a panorama image exists, then the panorama image is subject to caching. The response header does not include Cache-Control, etc., but includes Last-Modified instead.

The user agent can access conditionally with If-Modified-Since. If there is no update, then a no update response (304 Not Modified) is returned.

If no panorama image exists, then an HTTP error (404 Not Found) is returned.

### Parameters

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>
[c.<c>].panorama	The panorama number of camera number c (1 or higher). 0 is interpreted as 1.

### Responses

Content-Type	image/jpeg
Message body	<panorama image data>

### Error

Livescope-Status	Error details
401 Unknown Operator	An undefined command was specified. Required parameter is not specified.
501 Unknown Connection ID	Specified session does not exist.

### **Example of Parameters and Responses**

GET /-wvhttp-01-/panorama.cgi HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: xxxxx

Server: VB

{ Panorama image data }

## 2.6 Camera Control Commands

### 2.6.1 control.cgi

#### Format

```
http://<ipaddress>/-wvhttp-01-/control.cgi?[s=<session-id>][&c.priority  
][&c][&exp=value][&ae.autoss=value]...
```

#### Function Overview

This function controls the camera and external output terminal.

When controlling everything but the external output terminal (along with pan, tilt, and zoom speed), camera control privileges are necessary. If camera privileges cannot be secured, a 301 error is returned to Livescope-Status.

If camera control privileges are necessary, operations will differ as follows, depending on whether or not a session identifier <s> is specified:

When the session identifier is specified:

The camera will be controlled based on the session's camera control privileges.

The priority level specification is ignored.

When the session identifier is not specified:

An attempt is made to secure camera control privileges with the specified priority level, and if the attempt succeeds, camera control is performed. If the control privileges cannot be secured immediately, then the camera will not be controlled.

With control.cgi, it is possible to specify multiple commands simultaneously, however, when multiple commands are specified, not all commands may be processed correctly depending on the operation status.

Especially with commands that perform mechanical operations, such as pan and tilt operation, zoom operation, and day-night mode switching, note that substantial amount of time is required to complete the operation.

When each command is transmitted individually, it is recommended to be transmitted at intervals of 200 milliseconds or more.



When only pan, tilt, and zoom speed are to be changed, there is no need to secure the camera control privileges. If, however, other control items are also to be controlled in combination with these, then camera control privileges will be required, and if the control privilege cannot be secured, then pan, tilt, and zoom speed will also remain unchanged. The camera control parameter "<c>" is the camera number. When "c.<c>." is omitted, the currently selected camera is controlled. The values which can be specified for each control item depend on the model and operating state (for details, refer to the parameter description and Appendix A.3).

When sending a command with control.cgi, information such as operation target position in accordance with the specified command is notified with info.cgi. Subsequently, since a notification is performed with info.cgi in accordance with the status of state, the notification may be performed multiple times with info.cgi, depending on the status of state.

#### Parameters (VB-M40)

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>								
s.priority	Priority level (0: general user, 5 to 50: operator). Value defaults to 0 when omitted. Priority levels of users other than general users are restricted to the user, and priority levels between 1 and 4 are treated as 5 (1 to 4 are a reserved range).								
c	The camera number of the camera to switch to (1 or higher).								
[c.<c>].exp	Specifies the exposure mode. One of the following may be specified: <table border="1"> <tr> <td>auto</td><td>Automatic exposure (auto)</td></tr> <tr> <td>flickerfree</td><td>Automatic exposure (flickerless)</td></tr> <tr> <td>tv</td><td>Automatic exposure (shutter-priority AE)</td></tr> <tr> <td>manual</td><td>Manual exposure</td></tr> </table>	auto	Automatic exposure (auto)	flickerfree	Automatic exposure (flickerless)	tv	Automatic exposure (shutter-priority AE)	manual	Manual exposure
auto	Automatic exposure (auto)								
flickerfree	Automatic exposure (flickerless)								
tv	Automatic exposure (shutter-priority AE)								
manual	Manual exposure								
[c.<c>].ae.autoss	Specify the auto slow shutter. Specifies the shutter speed's reciprocal number. This is ignored if the exposure mode is set to manual.								
[c.<c>].ae.shutter	Specify the shutter speed. Specifies the shutter speed's reciprocal number. This is ignored unless the exposure mode is set to tv.								
[c.<c>].ae.brightness	Specify the backlight adjustment value. Specified as a numerical value (low [dark] to high [bright]; device-dependent). This is ignored if the exposure mode is set to manual.								

[c.<c>].jae.photometry	Specify the metering system. One of the following may be specified:	
	center	Center-weighted metering
	average	Average metering
	spot	Spot metering
	This is ignored if the exposure mode is set to manual.	
[c.<c>].me.shutter	Specify the shutter speed. Specify the shutter speed's reciprocal number. This is ignored unless the exposure mode is set to manual.	
[c.<c>].me.iris	Specify the aperture value. Specify a numerical value (low [opened] to high [closed]; device-dependent). This is ignored unless the exposure mode is set to manual.	
[c.<c>].me.gain	Specify the AGC gain value. Specify a numerical value (low to high; device-dependent). This is ignored unless the exposure mode is set to manual.	
[c.<c>].wb	Specify the white balance. One of the following may be specified:	
	auto	Automatic white balance
	manual	Manual white balance
	fluorescent_l	Fluorescent L (White cool)
	fluorescent_h	Fluorescent H (Daylight)
	fluorescent_w	Fluorescent Incandescent (Warm white)
	sodium	Sodium light
	halogen	Halogen light
	mercury	Mercury light
	one_shot	One-shot white balance
	When one_shot is specified, after white balance is corrected, it returns to manual white balance mode.	
[c.<c>].wb.value	Specify the RB gain. Specify the white balance in RRRR-BBBB format. This is ignored in modes other than manual white balance.	
[c.<c>].dn	Specify the day-night mode. Specify either on (or 1) or off (or 0). This is ignored in auto day-night mode. This item is restricted to privileged users (administrator/operator).	
[c.<c>].dn.mode	Specify the day-night switching mode. Specify either manual (for manual), or auto1 (auto). This item is restricted to privileged users (administrator/operator).	
[c.<c>].is	Specify the image stabilization function. Specify off, on1 (small), or on2 (large). This item is restricted to privileged users (administrator/operator).	
[c.<c>].nr	Specify the noise reduction level. Specify a numerical value (device-dependent).	
[c.<c>].ac	Specify the aperture correction value. Specify a numerical value (device-dependent).	

[c.<c>].shade	Specify the smart shade control. Specify either on (or 1) or off (or 0).														
[c.<c>].shade.param	Specify the smart shade control parameter. Specify a numerical value 0 or higher (a step value). The numerical value indicates the strength of smart shade control (low/weak to high/strong), but the actual effect will depend on the device settings and the image.														
[c.<c>].focus	<p>Specify the focus mode/Specify the focus operation. One of the following may be specified:</p> <table border="1"> <tr><td>auto</td><td>Auto focus</td></tr> <tr><td>manual</td><td>Manual focus</td></tr> <tr><td>infinity</td><td>Fixed at infinity</td></tr> <tr><td>one_shot</td><td>One-shot AF</td></tr> <tr><td>stop</td><td>Stop</td></tr> <tr><td>near</td><td>Move to near distance side</td></tr> <tr><td>far</td><td>Move to far distance side</td></tr> </table> <p>When one_shot is specified, after the device is focused at the current position, the mode reverts to manual focus. When stop, near, or far is specified, after manual mode is switched to, the prescribed operation is performed. The notification of manual mode is performed after the focus operation is completed. When stop is specified, it reverts to manual mode.</p>	auto	Auto focus	manual	Manual focus	infinity	Fixed at infinity	one_shot	One-shot AF	stop	Stop	near	Move to near distance side	far	Move to far distance side
auto	Auto focus														
manual	Manual focus														
infinity	Fixed at infinity														
one_shot	One-shot AF														
stop	Stop														
near	Move to near distance side														
far	Move to far distance side														
[c.<c>].focus.value	Specify the focus value. Specify a numerical value (device-dependent). This is ignored in modes other than manual focus. Since the focus value depends on the zoom position, when the zoom position changes, it may not focus even if the focus value is the same.														
[c.<c>].zoom	<p>Specify the zoom position or operation. One of the following may be specified:</p> <table border="1"> <tr><td>&lt;position&gt;</td><td>Moves to &lt;position&gt; (the horizontal angle of view in 0.01 degree units)</td></tr> <tr><td>d[±] &lt;difference&gt;</td><td>Moves to a position that is the current position ±&lt;difference&gt;</td></tr> <tr><td>v[+] &lt;magnification ratio&gt;</td><td>Moves to the &lt;magnification ratio&gt; position based on the current angle of view. Specify the &lt;magnification ratio&gt; with a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.</td></tr> <tr><td>stop</td><td>Stop</td></tr> <tr><td>tele</td><td>Move to the telephoto side</td></tr> <tr><td>wide</td><td>Move to the wide angle side</td></tr> </table>	<position>	Moves to <position> (the horizontal angle of view in 0.01 degree units)	d[±] <difference>	Moves to a position that is the current position ±<difference>	v[+] <magnification ratio>	Moves to the <magnification ratio> position based on the current angle of view. Specify the <magnification ratio> with a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.	stop	Stop	tele	Move to the telephoto side	wide	Move to the wide angle side		
<position>	Moves to <position> (the horizontal angle of view in 0.01 degree units)														
d[±] <difference>	Moves to a position that is the current position ±<difference>														
v[+] <magnification ratio>	Moves to the <magnification ratio> position based on the current angle of view. Specify the <magnification ratio> with a relative value (50 means a magnification ratio of 1/2, and 200 means double) with the current position as 100.														
stop	Stop														
tele	Move to the telephoto side														
wide	Move to the wide angle side														
[c.<c>].zoom.speed	Specify the following pos and dir.														
[c.<c>].zoom.speed.pos	The operational speed when a position is specified in c.<c>.zoom.														
[c.<c>].zoom.speed.dir	The operational speed when either tele or wide is specified in c.<c>.zoom.														

[c.<c>].pan	Specify the pan position or operation.	
	<position>	Moves to <position> (in 0.01 degree units, with the right side positive)
	d[±]<difference>	Moves to a position that is the current position ±<difference>
	v[±]<difference>	Moves to a position that is the current position ±<difference>. The difference is a relative position based on the screen, with 0 representing the center, -100 representing the left edge, and 100 representing the right edge.
	stop	Stop
	left	Move to the left
	right	Move to the right
[c.<c>].pan.speed	Specify the following pos and dir.	
[c.<c>].pan.speed.pos	The operational speed when a position is specified in c.<c>.pan.	
[c.<c>].pan.speed.dir	The operational speed when either left or right is specified in c.<c>.pan.	
[c.<c>].tilt	Specify the tilt position or operation.	
	<position>	Moves to <position> (in 0.01 degree units, with the up side positive)
	d[±]<difference>	Moves to a position that is the current position ±<difference>
	v[±]<difference>	Moves to a position that is the current position ±<difference>. The difference is a relative position based on the screen, with 0 representing the center, -100 representing the bottom edge, and 100 representing the top edge.
	stop	Stop
	up	Move up
	down	Move down
[c.<c>].tilt.speed	Specify the following pos and dir.	
[c.<c>].tilt.speed.pos	The operational speed when a position is specified in c.<c>.tilt.	
[c.<c>].tilt.speed.dir	The operational speed when either up or down is specified in c.<c>.tilt.	
[c.<c>].view.restriction	<p>Specify the restriction on the viewable range.</p> <p>Specify on (or 1) to turn this on, or off (or 0) to turn this off. This item is restricted to administrators and the session identifier &lt;s&gt; is necessary. The restriction of the viewable range is not changed when session identifier &lt;s&gt; is not specified.</p> <p>When the session, in which the restriction on the viewable range is off, loses the control privilege, the restriction becomes automatically on.</p>	

o.<0>	External output control. Specify on (or 1) to turn this on, or off (or 0) to turn this off. This item is restricted to privileged users (administrator, operator).
-------	--

When a control item is not specified, a 406 error is returned to Livescope-Status.

When this is sessionless, then if an item other than restriction of the viewable range or pan, tilt, or zoom speed, is not specified, a 406 error is returned to Livescope-Status.

When -0 is specified in specifying the difference (magnification ratio) of pan, tilt or zoom , a 403 error occurs.

### Parameters (VB-M600/VB-M700)

s	Specify the session identifier. <b>s=&lt;session id&gt;</b>								
s.priority	Priority level (0: general user, 5 to 50: operator). Value defaults to 0 when omitted. Priority levels of users other than general users are restricted to the user, and priority levels between 1 and 4 are treated as 5 (1 to 4 are a reserved range).								
c	The camera number of the camera to switch to (1 or higher).								
[c.<c>].exp	Specifies the exposure mode. One of the following may be specified: <table border="1"> <tr> <td>auto</td><td>Automatic exposure (auto)</td></tr> <tr> <td>flickerfree</td><td>Automatic exposure (flickerless)</td></tr> <tr> <td>tv</td><td>Automatic exposure (shutter-priority AE)</td></tr> <tr> <td>manual</td><td>Manual exposure</td></tr> </table>	auto	Automatic exposure (auto)	flickerfree	Automatic exposure (flickerless)	tv	Automatic exposure (shutter-priority AE)	manual	Manual exposure
auto	Automatic exposure (auto)								
flickerfree	Automatic exposure (flickerless)								
tv	Automatic exposure (shutter-priority AE)								
manual	Manual exposure								
[c.<c>].ae.autoss	Specify the auto slow shutter. Specifies the shutter speed's reciprocal number. This is ignored if the exposure mode is set to manual.								
[c.<c>].ae.shutter	Specify the shutter speed. Specifies the shutter speed's reciprocal number. This is ignored unless the exposure mode is set to tv.								
[c.<c>].ae.brightness	Specify the backlight adjustment value. Specified as a numerical value (low [dark] to high [bright]; device-dependent). This is ignored if the exposure mode is set to manual.								
[c.<c>].ae.photometry	Specify the metering system. One of the following may be specified: <table border="1"> <tr> <td>center</td><td>Center-weighted metering</td></tr> <tr> <td>average</td><td>Average metering</td></tr> <tr> <td>spot</td><td>Spot metering</td></tr> </table> This is ignored if the exposure mode is set to manual.	center	Center-weighted metering	average	Average metering	spot	Spot metering		
center	Center-weighted metering								
average	Average metering								
spot	Spot metering								
[c.<c>].me.shutter	Specify the shutter speed. Specify the shutter speed's reciprocal number. This is ignored unless the exposure mode is set to manual.								

[c.<c>].me.iris	Specify the aperture value. Specify a numerical value (low [opened] to high [closed]; device-dependent). This is ignored unless the exposure mode is set to manual.																		
[c.<c>].me.gain	Specify the AGC gain value. Specify a numerical value (low to high; device-dependent). This is ignored unless the exposure mode is set to manual.																		
[c.<c>].wb	Specify the white balance. One of the following may be specified: <table border="1"> <tr> <td>auto</td><td>Automatic white balance</td></tr> <tr> <td>manual</td><td>Manual white balance</td></tr> <tr> <td>fluorescent_l</td><td>Fluorescent L (White cool)</td></tr> <tr> <td>fluorescent_h</td><td>Fluorescent H (Daylight)</td></tr> <tr> <td>fluorescent_w</td><td>Fluorescent Incandescent (Warm white)</td></tr> <tr> <td>sodium</td><td>Sodium light</td></tr> <tr> <td>halogen</td><td>Halogen light</td></tr> <tr> <td>mercury</td><td>Mercury light</td></tr> <tr> <td>one_shot</td><td>One-shot white balance</td></tr> </table> When one_shot is specified, after white balance is corrected, it returns to manual white balance mode.	auto	Automatic white balance	manual	Manual white balance	fluorescent_l	Fluorescent L (White cool)	fluorescent_h	Fluorescent H (Daylight)	fluorescent_w	Fluorescent Incandescent (Warm white)	sodium	Sodium light	halogen	Halogen light	mercury	Mercury light	one_shot	One-shot white balance
auto	Automatic white balance																		
manual	Manual white balance																		
fluorescent_l	Fluorescent L (White cool)																		
fluorescent_h	Fluorescent H (Daylight)																		
fluorescent_w	Fluorescent Incandescent (Warm white)																		
sodium	Sodium light																		
halogen	Halogen light																		
mercury	Mercury light																		
one_shot	One-shot white balance																		
[c.<c>].wb.value	Specify the RB gain. Specify the white balance in RRRR-BBBB format. This is ignored in modes other than manual white balance.																		
[c.<c>].dn	Specify the day-night mode. Specify either on (or 1) or off (or 0). This is ignored in auto day-night mode. This item is restricted to privileged users (administrator/operator).																		
[c.<c>].dn.mode	Specify the day-night switching mode. Specify either manual (for manual), or auto1 (auto). This item is restricted to privileged users (administrator/operator).																		
[c.<c>].nr	Specify the noise reduction level. Specify a numerical value (device-dependent).																		
[c.<c>].ac	Specify the aperture correction value. Specify a numerical value (device-dependent).																		
[c.<c>].shade	Specify the smart shade control. Specify either on (or 1) or off (or 0).																		
[c.<c>].shade.param	Specify the smart shade control parameter. Specify a numerical value 0 or higher (a step value). The numerical value indicates the strength of smart shade control (low/weak to high/strong), but the actual effect will depend on the device settings and the image.																		

[c.<c>].focus	<p>Specify the focus mode/Specify the focus operation. One of the following may be specified:</p> <table border="1" data-bbox="651 342 1347 533"> <tr><td>manual</td><td>Manual focus</td></tr> <tr><td>infinity</td><td>Fixed at infinity</td></tr> <tr><td>one_shot</td><td>One-shot AF</td></tr> <tr><td>stop</td><td>Stop</td></tr> <tr><td>near</td><td>Move to near distance side</td></tr> <tr><td>far</td><td>Move to far distance side</td></tr> </table> <p>When one_shot is specified, after the device is focused at the current position, the mode reverts to manual focus. When stop, near, or far is specified, after manual mode is switched to, the prescribed operation is performed. When stop is specified, it reverts to manual mode.</p>	manual	Manual focus	infinity	Fixed at infinity	one_shot	One-shot AF	stop	Stop	near	Move to near distance side	far	Move to far distance side
manual	Manual focus												
infinity	Fixed at infinity												
one_shot	One-shot AF												
stop	Stop												
near	Move to near distance side												
far	Move to far distance side												
[c.<c>].focus.value	<p>Specify the focus value. Specify a numerical value (device-dependent). This is ignored in modes other than manual focus. Since the focus value depends on the zoom position, when the zoom position changes, it may not focus even if the focus value is the same.</p>												
o.<o>	<p>External output control. Specify on (or 1) to turn this on, or off (or 0) to turn this off. This item is restricted to privileged users (administrator, operator).</p>												

When a control item is not specified, a 406 error is returned to Livescope-Status.

## Responses

Content-Type	text/plain; charset=utf-8
Message body	<p>&lt;item name&gt;:=&lt;value&gt; ... An item whose state is changing &lt;item name&gt;==&lt;value&gt; ... An item whose state is not changing ...</p>
Notes	<p>Response to a specified parameter is returned to the message body of a response. If the state has changed, then this will be notified with an event. Parameters dependent on an ignored mode (dn, wb.value, etc.) return the response '&lt;item name&gt;==?'.</p>

## Error

Livescope-Status	Error details
401 Unknown Operator	<p>An undefined command was specified. Required parameter is not specified.</p>
501 Unknown Connection ID	Specified session does not exist.

### **Example of Parameters and Responses**

GET /-wvhttp-01-/control.cgi?dn=0HTTP/1.1

⇒

HTTP/1.1 200 OK

...

Livescope-Status: 0

Content-Length: 12

Server: VB

c.1.dn==off



# A VB-M40 Information Retrieval Items

This appendix shows a list of information that can be retrieved by the VB-M40.

The letters <c>, <p>, <i>, <o>, <r> and <a> in the table correspond to the following numbers (integer values).

Attributes are as follows:

C: control items (items that can be changed with control.cgi, etc.)

P: client-specific items (items that can be changed without affecting the operation of other clients)

U: items with update notifications (items that notify with info.cgi when changed)

Number	Meaning	Range	Notes
<c>	Camera number	1	
<p>	Preset number	1 to 20	Only in cases where the preset setting is valid
<i>	External input terminal number	1 to 2	
<o>	External output terminal number	1 to 2	
<r>	Intelligent Function rule number	1 to 16	
<a>	Audio input terminal number	1	

## A.1 System Information

Item Name	Meaning	Attributes	Notes
s	Session identifier	- P -	*a
s.origin	Address and port of the camera server	- P -	*a, *b
s.duration	Remaining time in session	- P U	*c
s.priority	Session's priority level	C P U	
s.control	State of camera control privileges	C P U	*d
s.epoch	Start-up time	- - U	
s.hardware	Model name	- - -	
s.firmware	Firmware version	- - -	
s.protocol	Protocol version	- - -	

*a	open.cgi command response only.		
*b	One of the following notations depending on the client type (IPv4 or IPv6), and whether or not there are NAT settings:  When a request is made in IPv6, a manual setting address is returned preferentially. If an address is not manually set, an address that can be acquired first among auto setting addresses is returned.  IPv6/no NAT setting    [<IPv6 address>]:HTTP port    e.g. [3FFE:2A00:100:7031::1]:80		
*c	IPv6/with NAT setting    [<IPv6 address>]:NAT port    e.g. 3FFE:2A00:100:7031::1:80		
*d	IPv4/no NAT setting    <IPv4 address>:HTTP port    e.g. 192.168.100.1:80  IPv4/with NAT setting    <NAT host>:<NAT port>    e.g. camera.jp:80  Numerical value: second units (decimal part rounded up), 0: unlimited.  enabled[:<allocated time>]: securing, waiting[:<waiting time>]: waiting to secure, disabled: none.  Time is a numerical value: millisecond units, unlimited: unlimited. Default value is disabled (not notified until change is made).		

## A.2 Video Information

Item Name	Meaning	Attributes	Notes
v	Selected stream	C P U	*a
v.list	Stream list	- - U	*a
*a    <jpg h264>:<screen width>x<screen height>:<image quality>:<frame rate>. Image quality is step values (same as the setting value: 1 to 5).			

## A.3 Camera Information

Item Name	Meaning	Attributes	Notes
c	Selected camera number	C - U	*a
c.count	Number of cameras	- - -	
c.<c>.type	Camera type	- - -	
c.<c>.status	State of operation	- - U	
c.<c>.name.asc	Camera name (ASCII)	- - U	
c.<c>.name.utf8	Camera name (UTF-8)	- - U	
c.<c>.name.lang	Camera name (UTF-8) setting language	- - U	*b
*a    enabled: can be controlled, disabled: cannot be controlled. Disabled right after startup, and *b    enabled after camera is initialized. en: English, ja: Japanese fr: French, it: Italian, de: German, es: Spanish  Only when corresponding c.<c>.name.utf8 is not blank.			

Item Name	Meaning	Attributes	Notes
c.<c>.exp	Exposure mode	C - U	*c
c.<c>.exp.list	Exposure mode list	- - -	*c
c.<c>.ae.autoss	Auto slow shutter	C - U	*d,*e
c.<c>.ae.autoss.list	Auto slow shutter list	- - -	*d

c.<c>.ae.shutter	Shutter speed	C - U	*d,*f
c.<c>.ae.shutter.list	Shutter speed list	- - -	*d
c.<c>.ae.brightness	Backlight adjustment value	C - U	*g
c.<c>.ae.brightness.min	Backlight adjustment value's minimum value	- - -	
c.<c>.ae.brightness.max	Backlight adjustment value's maximum value	- - -	
c.<c>.ae.brightness.list	Backlight adjustment value list	- - -	
c.<c>.ae.photometry	Metering system	C - U	*g,*h
c.<c>.ae.photometry.list	Metering system list	- - -	*h
c.<c>.me.shutter	Shutter speed	C - U	*d,*i
c.<c>.me.shutter.list	Shutter speed list	- - -	
c.<c>.me.iris	Aperture value	C - U	*i
c.<c>.me.iris.min	Aperture value's minimum value	- - -	
c.<c>.me.iris.max	Aperture value's maximum value	- - -	
c.<c>.me.gain	Gain value	C - U	*i
c.<c>.me.gain.min	Gain value's minimum value	- - -	
c.<c>.me.gain.max	Gain value's maximum value	- - -	
c.<c>.dn	Infrared cutting filter insertion state	C - U	*n
c.<c>.dn.mode	Infrared cutting filter control mode	C - U	*k
c.<c>.dn.mode.list	Infrared cutting filter control mode list	- - -	*k
c.<c>.wb	White balance mode	C - U	*l
c.<c>.wb.list	White balance mode list	- - -	*l
c.<c>.wb.value	RB gain value	C - U	*m
c.<c>.is	Image stabilization	C - U	*j
c.<c>.nr	Noise reduction level	C - U	
c.<c>.nr.min	Noise reduction level minimum value	- - -	
c.<c>.nr.max	Noise reduction level maximum value	- - -	
c.<c>.ac	Aperture correction level	C - U	
c.<c>.ac.min	Aperture correction level minimum value	- - -	
c.<c>.ac.max	Aperture correction level maximum value	- - -	
c.<c>.shade	Smart shade control	C - U	
c.<c>.shade.param	Smart shade control parameter	C - U	
c.<c>.shade.param.min	Smart shade control parameter minimum value	- - -	
c.<c>.shade.param.max	Smart shade control parameter maximum value	- - -	

*c	auto: auto, flickerfree: auto (flickerless), tv: auto (shutter-priority AE), manual: manual.
*d	shutter speed's reciprocal number.
*e	c.<c>.exp = only when auto is set.
*f	c.<c>.exp = only when tv is set.
*g	c.<c>.exp = only when other than manual is set.
*h	center: center-weighted, average: average, spot: spot.
*i	c.<c>.exp = only when manual is set. When switching to manual mode, control range (min/max) may exceed.
*j	off: off, on1: for small vibration, on2: for large vibration.
*k	manual: manual, auto1: auto 1.
*l	auto: auto, manual: manual, etc.
*m	c.<c>.wb = only when manual is set.
*n	off: day mode, on: night mode

Item Name	Meaning	Attributes	Notes
c.<c>.focus	Focus mode	C - U	*m
c.<c>.focus.list	Focus mode list	- - -	*m
c.<c>.focus.value	Focus value	C - U	*n
c.<c>.zoom	Zoom value	C - U	*o
c.<c>.zoom.d	Digital zoom boundary value (optical telephoto boundary)	- - -	*o
c.<c>.zoom.min	Zoom telephoto side control limit	- - U	*o
c.<c>.zoom.max	Zoom wide side control limit	- - U	*o
c.<c>.zoom.limit.min	Zoom telephoto side movement limit	- - -U	*o
c.<c>.zoom.limit.max	Zoom wide side movement limit	- - -	*o
c.<c>.zoom.speed.pos	Position-specified zoom speed	C P -	
c.<c>.zoom.speed.dir	Operation-specified zoom speed	C P -	
c.<c>.zoom.speed.min	Minimum zoom speed	- - -	
c.<c>.zoom.speed.max	Maximum zoom speed	- - -	
<p>*m Auto: auto, infinity: fixed at infinity, manual: manual.</p> <p>*n c.&lt;c&gt;.focus = only when manual is set.</p> <p>*o Compatible to control parameters of optical systems, it is expressed in horizontal angle of view (1=0.01 degree), however, actual value available is discreet (optical resolution dependent, it is rough on the wide-angle end, and fine on the telephoto-angle end).</p> <p>The effective angle of view will become narrow when the image stabilization function is turned on, and digital zoom control range will also decrease (on1:5/6, on2:1/2).</p>			

Item Name	Meaning	Attributes	Notes
c.<c>.pan	Pan position	C - U	*p
c.<c>.pan.min	Camera platform left side control limit	- - U	*p
c.<c>.pan.max	Camera platform right side control limit	- - U	*p
c.<c>.pan.limit.min	Camera platform left side movement limit	- - -	*p
c.<c>.pan.limit.max	Camera platform right side movement limit	- - -	*p
c.<c>.pan.speed.pos	Position-specified pan speed	C P -	
c.<c>.pan.speed.dir	Operation-specified pan speed	C P -	
c.<c>.pan.speed.min	minimum pan speed	- - -	
c.<c>.pan.speed.max	maximum pan speed	- - -	
c.<c>.tilt	Tilt position	C - U	*p
c.<c>.tilt.min	Camera platform bottom side control limit	- - U	*p
c.<c>.tilt.max	Camera platform top side control limit	- - U	*p
c.<c>.tilt.limit.min	Camera platform bottom side movement limit	- - -	*p
c.<c>.tilt.limit.max	Camera platform top side movement limit	- - -	*p
c.<c>.tilt.speed.pos	Position-specified tilt speed	C P -	
c.<c>.tilt.speed.dir	Operation-specified tilt speed	C P -	
c.<c>.tilt.speed.min	Minimum tilt speed	- - -	
c.<c>.tilt.speed.max	Maximum tilt speed	- - -	
<p>*p Front is expressed in 0/0, right/top is expressed in a positive angle (1=0.01 degree). Actual value available is discreet (position of the camera platform resolution dependent), and the range of value is installation location (upright/ceiling) dependent.</p> <p>c.&lt;c&gt;.pan.min, c.&lt;c&gt;.pan.max, c.&lt;c&gt;.pan.min, and c.&lt;c&gt;.pan.max are pan/tilt control ranges at zoom telephoto limit (pan/tilt control range will differ depending on zoom position when restriction on visible range is applied).</p>			

Item Name	Meaning	Attributes	Notes
c.<c>.view	Visible range	- - U	*q
c.<c>.view.restriction	Restriction on Visible range	C - U	*r
<p>*q &lt;left boundary&gt;:&lt;top boundary&gt;:&lt;width&gt;:&lt;height&gt; (1=0.01 degree). Actual value available is generally discreet, however, it is pan/tilt/zoom value combination dependent.</p> <p>*r The control is limited to the administrator.</p>			

Item Name	Meaning	Attributes	Notes
c.<c>.panorama.count	Number of panorama images	- - -	
c.<c>.panorama.1.view	Panorama image view field information	- - -	*s
c.<c>.panorama.1.image	Panorama image information	- - -	*t
c.<c>.panorama.1.timestamp	Panorama image time stamp	- - U	*u
*s <left boundary>:<top boundary>:<width>:<height> (in 0.01 degrees unit). *t <width>x<height>:<image quality>:<size>. *u <day of the week>, <day> <month> <year> <hour>:<minute>:<second> <time zone>.			

## A.4 External Input/Output Information

Item Name	Meaning	Attributes	Notes
i.count	Number of external input terminals	- - -	
i.<i>	External input terminal<i> status	- - U	*a
i.<i>.name.asc	External input terminal name (ASCII)	- - U	
i.<i>.name.utf8	External input terminal name (UTF-8)	- - U	
i.<i>.name.lang	External input terminal name (UTF-8) setting language	- - U	*b
o.count	Number of external output terminals	- - -	
o.<o>	External output terminal<i> status	C - U	*a
o.<o>.name.asc	External output terminal name (ASCII)	- - U	
o.<o>.name.utf8	External output terminal name (UTF-8)	- - U	
o.<o>.name.lang	External output terminal name (UTF-8) setting language	- - U	*b
*a 0: off, 1: on- *b en: English, ja: Japanese, fr: French, it Italian, de: German, es: Spanish Only when corresponding i.<i>.name.utf8, o.<o>.name.utf8, or m.<m>.name.utf8 is not blank.			

## A.5 Preset Information

Item Name	Meaning	Attributes	Notes
p.count	Number of presets	- - U	
p.<p>.name.asc	Preset <p> name (ASCII)	- - U	
p.<p>.name.utf8	Preset <p> name (UTF-8)	- - U	
p.<p>.name.lang	Preset <p> name (UTF-8) setting language	- - U	*a
p.<p>.c	Preset <p> camera number	- - U	
p.<p>.pan	Preset <p> pan value	- - U	
p.<p>.tilt	Preset <p> tile value	- - U	
p.<p>.zoom	Preset <p> zoom value	- - U	

p.<p>.focus	Preset <p> focus value	- - U	*b
p.<p>.ae.brightness	Preset <p> backlight compensation value	- - U	
p.<p>.shade	Preset <p> smart shade control	- - U	*c
p.<p>.shade.param	Preset <p> smart shade control parameter	- - U	
p.<p>.wb	Preset <p> white balance mode	- - U	*d
p.<p>.wb.value	Preset <p> RB gain value	- - U	
<p>*a en: English, ja: Japanese, fr: French, it: Italian, de: German, es: Spanish Only when corresponding p.&lt;p&gt;.name.utf8 is not blank.</p> <p>*b c.&lt;c&gt;.focus.list element for supported camera. Manual is manual:&lt;focus value&gt;.</p> <p>*c 0: off, 1: on</p> <p>*d auto: auto, manual: manual, etc.</p>			

## A.6 Intelligent Function Information

Item Name	Meaning	Attributes	Notes
r.engine	Intelligent Function status	- - U	*a
r.meta	Whether or not metadata is embedded in the JPEG header	C - U	*b
r.pseudo	Detection status of a pseudo setting	- - U	*c
r.count	Detection rule number of the Intelligent Function	- - U	
r.<r>	Rule <r> detection status	- - U	*d
r.<r>.name.asc	Rule <r> name (ASCII)	- - U	
r.<r>.name.utf8	Rule <r> name (UTF-8)	- - U	
r.<r>.name.lang	Rule <r> name (UTF-8) setting language	- - U	*d
r.<r>.type	Rule <r> detection type	- - U	*f
<p>*a 0: off, 1: on, -1: invalid</p> <p>*b 0: off, 1: on</p> <p>*c 0: off, 1: on</p> <p>*d 0: off, 1: on</p> <p>*e En: English, ja: Japanese, fr: French, it: Italian, de: German, es: Spanish Only when corresponding r.&lt;r&gt;.name.utf8 is not blank.</p> <p>*f 0: unspecified, 1: moving object detection, 2: abandoned object detection, 3: removed object detection, 4: camera tampering detection, 5 - 15: reserved area</p>			

## A.7 Sound Device Information

Item Name	Meaning	Attributes	Notes
a.count	Number of sound devices	- - U	
a.<a>.send	Sound transmission from the camera	- - U	*a
a.<a>.recv	Receive sound from client	- - U	*b
a.<a>.detect	Detection status of input terminal of sound device <a>	- - U	*c
*a off: invalid, on: valid (equivalent to <hb00> of the setting protocol) *b off: invalid, on: valid (equivalent to <hb10> of the setting protocol) *c 0: off, 1: on, -1: invalid			

## A.8 External Memory Information

Item Name	Meaning	Attributes	Notes
f.sd	Mount status of the SD memory card.	- - U	*a
*a 0: unmount, 1: mount, 2: mount (write protect)			



## B VB-M600/VB-M700 Information Retrieval

### Items

This appendix shows a list of information that can be retrieved by the VB-M600/VB-M700.

The letters <c>, <p>, <i>, <o>, <r> and <a> in the table correspond to the following numbers (integer values).

Attributes are as follows:

C: control items (items that can be changed with control.cgi, etc.)

P: client-specific items (items that can be changed without affecting the operation of other clients)

U: items with update notifications (items that notify with info.cgi when changed)

Number	Meaning	Range	Notes
<c>	Camera number	1	
<p>	Preset number	0	The preset function is not supported.
<i>	External input terminal number	1 to 2	
<o>	External output terminal number	1 to 2	
<r>	Intelligent Function rule number	1 to 16	
<a>	Audio input terminal number	1	

### B.1 System Information

Item Name	Meaning	Attributes	Notes
s	Session identifier	- P -	*a
s.origin	Address and port of the camera server	- P -	*a, *b
s.duration	Remaining time in session	- P U	*c
s.priority	Session's priority level	C P U	
s.control	State of camera control privileges	C P U	*d
s.epoch	Start-up time	- - U	
s.hardware	Model name	- - -	
	(VB-M600VE/VB-M600D/VB-M700F )	- - -	
s.firmware	Firmware version	- - -	
s.protocol	Protocol version		

*a	open.cgi command response only.
*b	One of the following notations depending on the client type (IPv4 or IPv6), and whether or not there are NAT settings:  When a request is made in IPv6, a manual setting address is returned preferentially. If an address is not manually set, an address that can be acquired first among auto setting addresses is returned.  IPv6/no NAT setting    [<IPv6 address>]:HTTP port    e.g. [3FFE:2A00:100:7031::1]:80 IPv6/with NAT setting    [<IPv6 address>]:NAT port    e.g. 3FFE:2A00:100:7031::1]:80 IPv4/no NAT setting    <IPv4 address>:HTTP port    e.g. 192.168.100.1:80 IPv4/with NAT setting    <NAT host>:<NAT port>    e.g. camera.jp:80
*c	Numerical value: second units (decimal part rounded up), 0: unlimited.
*d	enabled[:<allocated time>]: securing, waiting[:<waiting time>]: waiting to secure, disabled: none.  Time is a numerical value: millisecond units, unlimited: unlimited. Default value is disabled (not notified until change is made).

## B.2 Video Information

Item Name	Meaning	Attributes	Notes
v	Selected stream	C P U	*a
v.list	Stream list	- - U	*a
v.h264.cbr	H.264 target bit rate	- - -	
*a <jpg h264>:<screen width>x<screen height>:<image quality>:<frame rate>. Image quality is step values (same as the setting value: 1 to 5).			

## B.3 Camera Information

Item Name	Meaning	Attributes	Notes
c	Selected camera number	C - U	
c.count	Number of cameras	- - -	
c.<c>.type	Camera type	- - -	
c.<c>.status	State of operation	- - U	*a
c.<c>.name.asc	Camera name (ASCII)	- - U	
c.<c>.name.utf8	Camera name (UTF-8)	- - U	
c.<c>.name.lang	Camera name (UTF-8) setting language	- - U	*b
*a enabled: can be controlled, disabled: cannot be controlled. Disabled right after startup, and enabled after camera is initialized.			
*b en: English, ja: Japanese fr: French, it: Italian, de: German, es: Spanish  Only when corresponding c.<c>.name.utf8 is not blank.			

Item Name	Meaning	Attributes	Notes
c.<c>.exp	Exposure mode	C - U	*c
c.<c>.exp.list	Exposure mode list	- - -	*c
c.<c>.ae.autoss	Auto slow shutter	C - U	*d,*e
c.<c>.ae.autoss.list	Auto slow shutter list	- - -	*d
c.<c>.ae.shutter	Shutter speed	C - U	*d,*f
c.<c>.ae.shutter.list	Shutter speed list	- - -	*d
c.<c>.ae.brightness	Backlight adjustment value	C - U	*g
c.<c>.ae.brightness.min	Backlight adjustment value's minimum value	- - -	
c.<c>.ae.brightness.max	Backlight adjustment value's maximum value	- - -	
c.<c>.ae.brightness.list	Backlight adjustment value list	- - -	
c.<c>.ae.photometry	Metering system	C - U	*g,*h
c.<c>.ae.photometry.list	Metering system list	- - -	*h
c.<c>.me.shutter	Shutter speed	C - U	*d,*i
c.<c>.me.shutter.list	Shutter speed list	- - -	
c.<c>.me.iris	Aperture value	C - U	*i
c.<c>.me.iris.min	Aperture value's minimum value	- - -	
c.<c>.me.iris.max	Aperture value's maximum value	- - -	
c.<c>.me.gain	Gain value	C - U	*i
c.<c>.me.gain.min	Gain value's minimum value	- - -	
c.<c>.me.gain.max	Gain value's maximum value	- - -	
c.<c>.dn	Infrared cutting filter insertion state	C - U	*n
c.<c>.dn.mode	Infrared cutting filter control mode	C - U	*k
c.<c>.dn.mode.list	Infrared cutting filter control mode list	- - -	*k
c.<c>.wb	White balance mode	C - U	*l
c.<c>.wb.list	White balance mode list	- - -	*l
c.<c>.wb.value	RB gain value	C - U	*m
c.<c>.nr	Noise reduction level	C - U	
c.<c>.nr.min	Noise reduction level minimum value	- - -	
c.<c>.nr.max	Noise reduction level maximum value	- - -	
c.<c>.ac	Aperture correction level	C - U	
c.<c>.ac.min	Aperture correction level minimum value	- - -	
c.<c>.ac.max	Aperture correction level maximum value	- - -	
c.<c>.shade	Smart shade control	C - U	
c.<c>.shade.param	Smart shade control parameter	C - U	
c.<c>.shade.param.min	Smart shade control parameter minimum value	- - -	

c.<c>.shade.param.max	Smart shade control parameter maximum value	- - -	
<p>*c auto: auto, flickerfree: auto (flickerless), tv: auto (shutter-priority AE), manual: manual.</p> <p>*d shutter speed's reciprocal number.</p> <p>*e c.&lt;c&gt;.exp = only when auto is set.</p> <p>*f c.&lt;c&gt;.exp = only when tv is set.</p> <p>*g c.&lt;c&gt;.exp = only when other than manual is set.</p> <p>*h center: center-weighted, average: average, spot: spot.</p> <p>*i c.&lt;c&gt;.exp = only when manual is set. When switching to manual mode, control range (min/max) may exceed.</p> <p>*j off: off, on1: for low amplitude, on2: for large amplitude</p> <p>*k manual: manual, auto1: auto 1.</p> <p>*l auto: auto, manual: manual, etc.</p> <p>*m c.&lt;c&gt;.wb = only when manual is set.</p> <p>*n off: day mode, on: night mode</p>			

Item Name	Meaning	Attributes	Notes
c.<c>.focus	Focus mode	C - U	*m
c.<c>.focus.list	Focus mode list	- - -	*m
c.<c>.focus.value	Focus value	C - U	*n
<p>*m infinity: fixed at infinity, manual: manual.</p> <p>*n c.&lt;c&gt;.focus = only when manual is set.</p>			

Item Name	Meaning	Attributes	Notes
c.<c>.panorama.count	Number of panorama images	- - -	*s
*s Fixed at 0			

## B.4 External Input/Output Information

Item Name	Meaning	Attributes	Notes
i.count	Number of external input terminals	- - -	
i.<i>	External input terminal<i> status	- - U	*a
i.<i>.name.asc	External input terminal name (ASCII)	- - U	
i.<i>.name.utf8	External input terminal name (UTF-8)	- - U	
i.<i>.name.lang	External input terminal name (UTF-8) setting language	- - U	*b
o.count	Number of external output terminals	- - -	
o.<o>	External output terminal<i> status	C - U	*a
o.<o>.name.asc	External output terminal name (ASCII)	- - U	
o.<o>.name.utf8	External output terminal name (UTF-8)	- - U	
o.<o>.name.lang	External output terminal name (UTF-8) setting language	- - U	*b
*a 0: off, 1: on *b en: English, ja: Japanese, fr: French, it Italian, de: German, es: Spanish Only when corresponding i.<i>.name.utf8, o.<o>.name.utf8, or m.<m>.name.utf8 is not blank.			

## B.5 Preset Information

Item Name	Meaning	Attributes	Notes
p.count	Number of presets	- - -	Always 0

## B.6 Intelligent Function Information

Item Name	Meaning	Attributes	Notes
r.engine	Intelligent Function status	- - U	*a
r.meta	Whether or not metadata is embedded in the JPEG header	C - U	*b
r.pseudo	Detection status of a pseudo setting	- - U	*c
r.count	Detection rule number of the Intelligent Function	- - U	
r.<r>	Rule <r> detection status	- - U	*d
r.<r>.name.asc	Rule <r> name (ASCII)	- - U	
r.<r>.name.utf8	Rule <r> name (UTF-8)	- - U	
r.<r>.name.lang	Rule <r> name (UTF-8) setting language	- - U	*d
r.<r>.type	Rule <r> detection type	- - U	*f

*a	0: off, 1: on, -1: invalid
*b	0: off, 1: on
*c	0: off, 1: on
*d	0: off, 1: on
*e	En: English, ja: Japanese, fr: French, it: Italian, de: German, es: Spanish Only when corresponding r.<r>.name.utf8 is not blank.
*f	0: unspecified, 1: moving object detection, 2: abandoned object detection, 3: removed object detection, 4: camera tampering detection, 5 to 9: reserved area, 10 to 15: Sler area

## B.7 Sound Device Information

Item Name	Meaning	Attributes	Notes
a.count	Number of sound devices	- - U	
a.<a>.send	Sound transmission from the camera	- - U	*a
a.<a>.recv	Receive sound from client	- - U	*b
a.<a>.detect	Detection status of input terminal of sound device <a>	- - U	*c
*a off: invalid, on: valid (equivalent to <hb00> of the setting protocol) *b off: invalid, on: valid (equivalent to <hb10> of the setting protocol) *c 0: off, 1: on, -1: invalid			

## B.8 External Memory Information

Item Name	Meaning	Attributes	Notes
f.sd	Mount status of the SD memory card.	- - U	*a
*a 0: unmount, 1: mount, 2: mount (write protect)			

## C Former Model Command

### C.1 Correspondence for Each Type of Information

Although commands of former models are supported in VB-M40/VB-M600/VB-M700, use the commands printed in this specifications since proper operation is not guaranteed.

Retrieval commands and item names were not always unified for commands of former models, and some items could not be retrieved. Although it is not possible to completely associate all commands of VB-M40/VB-M600/VB-M700 with commands of former models, the basic correspondence is as shown below:

New Command	Compatible Command	Item Name for Compatible Command
s	OpenCameraServer	connection_id
s.duration	GetSystemInfo	connection_time_limit
s.priority	Priority	priority
s.control	GetNotice	Event 31 to 34
s.epoch	GetSystemInfo	start_time
s.hardware	GetCameraServerInfo	modelName
	GetSystemInfo	version
s.firmware	GetCameraServerInfo	firmVersion
	GetSystemInfo	version
s.protocol	GetProtocolVersion	
v	GetVideoInfo	image_width
		image_height
		compression_type
		image_quality
		frame_rate
v.list	GetCameraServerInfo	image_size
		image_quality
c	GetCameraInfo	camera_id
c.count	GetCameraServerInfo	number_of_available_cameras
	GetCameraList	number_of_cameras
c.<c>.type	GetCameraInfo	camera_type
c.<c>.status	GetCameraInfo	camera_status
c.<c>.name.asc	GetCameraList	camera_129 ...
c.<c>.name.utf8	GetCameraList	camera_129 ...

c.<c>.name.lang	N/A	
c.<c>.exp	Exposure	
c.<c>.exp.list	GetCameraInfoEx	manual_ex
c.<c>.ae.autoss	GetCameraInfoEx	auto_slow_shutter_ex
c.<c>.ae.autoss.list	N/A	
c.<c>.ae.shutter	OperateCameraEx	shutter
c.<c>.ae.shutter.list	N/A	
c.<c>.ae.brightness	OperateCameraEx	brightness
	GetCameraInfo	back_light
c.<c>.ae.brightness.min	N/A	
c.<c>.ae.brightness.max	N/A	
c.<c>.ae.brightness.list	N/A	
c.<c>.ae.photometry	N/A	
c.<c>.ae.photometry.list	N/A	
c.<c>.me.shutter	Exposure	shutter
c.<c>.me.shutter.list	GetCameraInfoEx	shutter_speed_1 ...
c.<c>.me.iris	Exposure	iris
c.<c>.me.iris.min	GetCameraInfoEx	iris_min
c.<c>.me.iris.max	GetCameraInfoEx	iris_max
c.<c>.me.gain	Exposure	gain
c.<c>.me.gain.min	GetCameraInfoEx	gain_min
c.<c>.me.gain.max	GetCameraInfoEx	gain_max
c.<c>.dn	NightMode	night_mode
c.<c>.dn.list	N/A	
c.<c>.dn.mode	N/A	
c.<c>.dn.mode.list	N/A	
c.<c>.wb	GetCameraInfo	white_balance
c.<c>.wb.list	N/A	
c.<c>.wb.value	GetCameraInfo	rb_gain
c.<c>.is	N/A	
c.<c>.nr	NRLevel	nr_level
c.<c>.nr.min	N/A	
c.<c>.nr.max	N/A	
c.<c>.ac	N/A	
c.<c>.ac.min	N/A	
c.<c>.ac.max	N/A	



c.<c>.shade	N/A	
c.<c>.shade.param	N/A	
c.<c>.shade.param.min	N/A	
c.<c>.shade.param.max	N/A	
c.<c>.focus	GetCameraInfo	focus_mode
c.<c>.focus.value	GetCameraInfo	focus_value
c.<c>.focus.list	GetCameraInfoEx	far_fixed_focus
		dome_focus
		one_shot_focus
c.<c>.zoom	GetCameraInfo	zoom_current_value
c.<c>.zoom.d	GetCameraInfoEx	digital_zoom_boundary
c.<c>.zoom.min	GetCameraInfo	zoom_tele_limit
	GetCameraInfo	view_tele_boundary
c.<c>.zoom.max	GetCameraInfo	zoom_wide_limit
	GetCameraInfo	view_wide_boundary
c.<c>.zoom.limit.min	GetCameraInfo	zoom_tele_end
c.<c>.zoom.limit.max	GetCameraInfo	zoom_wide_end
c.<c>.zoom.speed.pos	GetPTZSpeedInfo	point_z
c.<c>.zoom.speed.dir	GetPTZSpeedInfo	direction_z
c.<c>.zoom.speed.min	GetPTZSpeedInfo	point_z_min / direction_z_min
c.<c>.zoom.speed.max	GetPTZSpeedInfo	point_z_max / direction_z_max
c.<c>.pan	GetCameraInfo	pan_current_vau
c.<c>.pan.min	GetCameraInfo	pan_left_limit
c.<c>.pan.max	GetCameraInfo	pan_right_limit
c.<c>.pan.limit.min	GetCameraInfo	pan_left_end
c.<c>.pan.limit.max	GetCameraInfo	pan_right_end
c.<c>.pan.speed.pos	GetPTZSpeedInfo	point_p
c.<c>.pan.speed.dir	GetPTZSpeedInfo	direction_p
c.<c>.pan.speed.min	GetPTZSpeedInfo	point_p_min / direction_p_min
c.<c>.pan.speed.max	GetPTZSpeedInfo	point_p_max / direction_p_max
c.<c>.tilt	GetCameraInfo	tilt_current_vau
c.<c>.tilt.min	GetCameraInfo	tilt_down_limit
c.<c>.tilt.max	GetCameraInfo	tilt_up_limit
c.<c>.tilt.limit.min	GetCameraInfo	tilt_down_end
c.<c>.tilt.limit.max	GetCameraInfo	tilt_up_end
c.<c>.tilt.speed.pos	GetPTZSpeedInfo	point_t

c.<c>.tilt.speed.dir	GetPTZSpeedInfo	direction_t
c.<c>.tilt.speed.min	GetPTZSpeedInfo	point_t_min / direction_t_min
c.<c>.tilt.speed.max	GetPTZSpeedInfo	point_t_max / direction_t_max
c.<c>.view	GetCameraInfo	view_left_boundary view_right_boundary view_up_boundary view_down_boundary
c.<c>.view.restriction	N/A	
c.<c>.panorama.count	GetPanoramaList	number_of_panorama_images
c.<c>.panorama.<c>.view	GetPanoramaInfo	pano_left
	GetPanoramaInfo	pano_top
	GetPanoramaInfo	pano_width
	GetPanoramaInfo	pano_height
c.<c>.panorama.<c>.image	GetPanoramaInfo	image_width
	GetPanoramaInfo	image_height
	GetPanoramaInfo	image_quality
	GetPanoramaInfo	image_size
c.<c>.panorama.<c>.timestamp	GetPanoramaInfo	date_and_time
i.count	ExternalIOConfig	number_of_input
i.<i>	ExternalIOStatus	i1 ...
i.<i>.name.asc	ExternalIOCaption	i1 ...
i.<i>.name.utf8	ExternalIOCaption	i1 ...
i.<i>.name.lang	N/A	
o.count	ExternalIOConfig	number_of_output
o.<o>	ExternalIOStatus	o1 ...
o.<o>.name.asc	ExternalIOCaption	o1 ...
o.<o>.name.utf8	ExternalIOCaption	o1 ...
o.<o>.name.lang	N/A	
m.count	ExternalIOConfig	md
m.<m>	ExternalIOStatus	d1
m.<m>.name.asc	N/A	
m.<m>.name.utf8	N/A	
m.<m>.name.lang	N/A	
p.count	GetPresetList	number_of_camera_positions
p.<p>.name.asc	GetPresetList	position_1 ...
p.<p>.name.utf8	GetPresetList	position_1 ...

p.<p>.name.lang	N/A	
p.<p>.c	GetPresetList	camera_id
p.<p>.pan	GetPresetList	pan
p.<p>.tilt	GetPresetList	tilt
p.<p>.zoom	GetPresetList	zoom
p.<p>.focus	GetPresetList	focus_mode
	GetPresetList	focus_value
p.<p>.ae.brightness	GetPresetList	back_light

# D JPEG Header Information

This appendix explains mainly JPEG image Header when using the Canon Network Cameras. The JPEG image Header is a Header with information written in the JPEG area using the APP0 marker.

[Note] In this document, a hexadecimal number is expressed with a letter ‘h’ appended at the end. (Example: 12h)

## JPEG Area MAP

JPEG area starts with SOI (Start of Image) at the head as shown in Fig.1, consists of JPEG image Header (APP0 area), reserved range, JPEG image data (encoding bit stream) and others, and ends with EOI (End of Image).

JPEG image Header is the area within the dotted line frame in Fig. 1.




Fig. 1

Encoding Bit Stream  
(FFDBh -)

FF E0: APP0 application marker  
00 52: APP0 area size (size excluding the 2byte for application marker = 82 bytes)

## JPEG Image Header (APP0)

The Table 2-1 below explains additional JPEG image Header information (excluding APP0 application marker and APP0 area size) in the Canon Network Cameras.

Table 2-1

Additional Information	Data Type	Description of Additional Information
Magic number	U<3>	V' and 'B' (Fixed at 56 42 00h)
Camera	U<1>	Camera number (Fixed at 01h)
Pan	U<2>	Pan angle when shooting (1/100 degree units)
Tilt	U<2>	Tilt angle when shooting (1/100 degree units)
Zoom	U<2>	Optical zoom angle when shooting (1/100 degree units)
Brightness	S<2>	Exposure setting when shooting (00h: invalid, 01h: Normal, 02h: Bright)
Shooting Time	U<4>	Shooting time (The number of seconds difference from 1970/1/1 00:00:00 GMT)
Time Zone	S<2>	Offset from GMT (minutes)
Image Quality	U<1>	JPEG image information
Model	U<1>	Model information
External Device Input Status	B[32]	External Device Input Status (B[0]: In1, B[1]: In2)
External Device Output Status	B[32]	External Device Output Status (B[0]: Out1)
File Format	U<1>	File Format (Fixed at 05h)
Authenticator Type	U<1>	No authenticator (Fixed at 00h)
Image Width	U<2>	Number of pixels in horizontal direction
Image Height	U<2>	Number of pixels in vertical direction
Fractions of Shooting Time	U<2>	Shooting time (millisecond-units)
Setting Value Identifier	U<4>	Integer value changed when changing settings
Server Identifier	B[24]	MAC address of Ethernet
Smart Shade Control	U<1>	Smart shade control value
Electronic Zoom Magnification	U<2>	Electronic zoom magnification when shooting
Exposure Compensation	S<2>	Exposure compensation value when shooting
MAC Address	B[48]	MAC address of Ethernet
Reservation 1	U<2>	Not used
Intelligent Function Status	B[32]	Intelligent Function status
Intelligent Function Rule Status	B[32]	Detection status of Intelligent Function rule
Reservation 2	U<16>	Not used

B[##]: ## represents the number of bits

S<##>: Signed integer, ## represents the number of bytes.

U<##>: Unsigned integer, ## represents the number of bytes.

For bit sequence, MSB is located at the head and integers are expressed in big-endian format.

## Item Description

Table 2-2

Item Name	Description
Magic number	Magic number representing an application with which an APP0 marker is created. In Canon Network Cameras, it is fixed at 'V' and 'B' (56 42 00h).
Camera	Camera number 01h: Main unit camera
Pan	Pan angle when shooting A value in 1/100 units, taking 0 for left 180 degrees, 18000 for the front (0 degree), and 36000 for right 180 degrees, is recorded.
Tilt	Tilt angle when shooting A value in 1/100 units, taking 0 stand for down 180 degrees, 18000 for horizontal plane (0 degree), and 36000 for up 180 degrees, is recorded.
Zoom	Optical zoom angle when shooting A value representing a viewing angle in the pan direction in 1/100 units is recorded.
Brightness	Exposure setting when shooting 0000h: invalid (Inoperable. Cameras without backlight compensation and exposure compensation functions) 0001h: Normal (backlight compensation and exposure compensation Off) 0002h: Bright (backlight compensation and exposure compensation On)
Shooting Time	Shooting time (The number of seconds difference from 1970/1/1 00:00:00 GMT) To be exact, it is a time when a JPEG image was generated in the camera, but not a time when the image was transmitted from the camera to the network.
Time Zone	Offset from GMT (Unit: minute)
Image Quality	JPEG image quality 00h: High compression to 04h: Low compression)
Model	(VB-M40:0Dh VB-M600VE:0Eh VB-M600D:0Fh VB-M700F:10h)
External Device Input Status	External device input status (0: Off, 1: On) B[0]:In1, B[1]:In2
External Device Output Status	External device output status(0: Off, 1: On) B[0]:Out1, B[1]:Out2, B[2]:Out3

Item Name	Description
File Format	File Format (Fixed at 05h)
Authenticator Type	No authenticator (Fixed at 00h)
Image Width	Number of pixels in horizontal direction In QVGA, 0140h (= hexadecimal representation of 320)
Image Height	Number of pixels in vertical direction In QVGA, 00F0h (= hexadecimal representation of 240)
Fractions of Shooting Time	Millisecond part of a shooting time
Setting Value Identifier	Integer value changed when changing settings (0)
Server Identifier	MAC address of Ethernet (last 3 bytes)
Smart Shade Control	Smart shade control value (0: Off, 1 to 7: Correction level)
Electronic Zoom Magnification	Electronic zoom magnification when shooting (00h: Digital Zoom OFF, 01h - : Digital Zoom Magnification(in 1/100 time units)
Exposure Compensation	Exposure compensation value when shooting ( -8 to +8)
MAC Address	MAC address of Ethernet (6 bytes)
Reservation 1	Not used (00 00h)
Intelligent Function Status	Intelligent Function status is expressed with bits 0th bit: Valid/Invalid of Intelligent Function status (1: Valid/0: Invalid) 1st bit: Valid/Invalid of Intelligent Function status rule (1: Valid/0: Invalid) 2nd bit: Valid/Invalid of preset fixing setting (1: Valid/0: Invalid) 3rd bit : Stay/Not stay at the preset position (1: Stay/0: Not stay)
Intelligent Function Rule Status	Detection status of Intelligent Function rule is expressed with bits. 1 to 15bit: Detection status of rules 1 to 15 * 0th bit is for work (0: Undetected, 1:Detecting)
Reservation 2	Not used (All are fixed at 00h)

## E H.264 Distribution Function

This appendix explains the H.264 image data distribution function employed by VB-M40/VB-M600/VB-M700.

### E.1 Image Parameters

Parameters for H.264 images supported by VB-M40/VB-M600/VB-M700 are as follows.

Table 2-3 H.264 Image Parameters

Parameter	Value	Default value	Setting Method	Notes
Image Size	1280x960 640x480 320x240	320x240	Setting Protocol	Reboot is required.
Frame Rate	10, 15, 30fps	30fps	Setting Protocol	Reboot is required.
Target Bit Rate	32kbps to 4Mbps	1Mbyte	Setting Protocol	In an mutually exclusive relationship with the Q value specification
Q Value	1 to 5	3	Setting Protocol	In an mutually exclusive relationship with the Bit rate control

1. Image Size  
160x120 size image is not supported.
2. Target Bit Rate  
It is used to specify a target bit rate and output at the set bit rate is not guaranteed.
3. Q Value (Image Quality)  
Even when the Q value is changed, this does not affect moov and moof headers.  
The Q value is stored in "slice\_qp\_delta" in the slice header.



# About Image Quality

When the target bit rate is set to a small value, the image quality may decrease and block noises be conspicuous especially in large size images.

## E.2 MP4 Fragment

The H.264 distribution part in the VB-M40/VB-M600/VB-M700 distributes H.264 image data in the MP4 fragment format. It handles a stream with only one video track. The video stream forms a MP4 format stream compliant with “ISO/IEC 14496-10” and “ISO/IEC 14496-15”. In other words, it creates a moov header and a moof header that are combined with picture data to be transmitted.

Detailed information on the moov and moof headers is prescribed by the standards, “ISO/IEC 14496-10” and “ISO/IEC 14496-15”.

Fragment Data Structure

The MP4 Fragment data structure for VB-M40/VB-M600/VB-M700 is shown in the Fig. below.

Each header of moov and moof follows the HTTP header and picture data for one fragment is transmitted following the mdat header.




Fig. 2 MP4Fragment Date Structure

1. Moov header

A moov header is distributed only once at the first of a fragment distribution. It includes mainly initial setting items necessary for video playback. For example, setting values such as image size, frame rate, time information are included in the moov header. A file size of each picture distributed together with the moov header is included in the stsz box. The head picture always begins with I picture.

“SPS”, “PPS” and “VUI” fields are added in order to support H.264 in VB-M40/VB-M600/VB-M700. All the fields are in “avcC”.

2. Time information when a distribution starts

When a distribution starts, a current time (second units) is stored in the “tkhd” and “mdhd” of a MP4 header. The time differs for each client. Also, it is not a time when an image was captured.

The current time is based on 1900/01/01 00:00 as the starting point.

3. SPS (Sequence Parameter Set) field

The SPS includes the profile and level of the entire sequences.

4. PPS (Picture Parameter Set) field

The PPS includes information regarding the entire pictures. However, The PPS does not include the setting value of Q value.

5. VUI (video Usability Information) field

The VUI includes information on aspect ratio, brightness and color space.

6. Moof header

The moof header includes a sequence number and frame type.

A file size of each picture distributed together with the moof header is included in the trun box. When “first\_sample\_flags” of the trun box is 0x0, the head picture of the fragment is I picture. When “first\_sample\_flags” of the trun box is a value other than 0x0, the head picture of the fragment is P picture.

## F HTTP Upload Specification

The HTTP upload function in the VB-M40/VB-M600/VB-M700 supports both event uploads and image uploads. It is possible to access via HTTP using the specified argument to HTTP server specified in the Setting Page and to upload image data when Image attached Notification is specified for Notification.

Events that serves as triggers for uploads can be set in Event under the Setting Page. There are the following three events that can be set as triggers.

- ✓ External Device Input

An event is triggered and an upload is performed when a sensor, etc. connected to an external device input terminal is turned on. An event can also be triggered when the sensor is turned off.

Each of External Device Input 1 and 2 can be used in VB-M40/VB-M600/VB-M700.

- ✓ Timer

Specify the Start Time, Repeat Interval and Repeat Count to cause to perform the upload operation at a certain intervals. The Repeat Count can be set in the range of 1 to 60. The Repeat Interval can be specified with one of the following values.

1 sec., 5 sec., 10 sec., 30 sec.,

1 min., 5 min., 10 min., 15 min., 20 min., 30 min.

1 hour, 3 hours, 6 hours, 12 hours

For the Repeat Count, the start time is counted as the first time. Therefore, when the Repeat Count is set to 1, an upload is performed only once at the start time.

- ✓ Intelligent Functions

Events are triggered by the Intelligent Functions including the Volume Detection and perform uploads.

For details, refer to VB-M40/VB-M600/VB-M700 Operation Guide.

There are the following setting items for the upload destination.

- Upload

Select from “Upload Disabled”, “HTTP Upload” and “FTP Upload”.

When “HTTP Upload” is selected, the following items can be set up.

Notification: Select from “Notification Only with HTTP” or “Image attached Notification with HTTP”.

URI: Specify URI for HTTP access.  
Example: `http://192.168.100.12:8080/cgi-bin/upload.cgi`

User Name: User name

Password: Password  
(Specify a user name and a password when the URI destination requires a user authentication. Only Basic Authentication is available.)

Proxy Server: Host name or IP address of a proxy server

Proxy Port: Port number of a proxy server  
(Specify this when accessing the URI via an HTTP proxy server.)

Proxy User Name: User name of a proxy server

Proxy Password: Password of a proxy server  
(Specify a user name and a password when the proxy server requires a user authentication. Only Basic Authentication is available.)

Parameter (query strings): Specify an URI parameter to be added to URI.  
The specified parameter can be used as query strings for CGI.

[Note]

An URI-encoded string should be specified for an URI parameter. (For the details for URI encoding, refer to RFC2396 "Uniform Resource Identifiers (URI): Generic Syntax")

Example: `filename=img&sensorNo=1`

Following '%' characters' can be used for parameters.

%n	Trigger of Shooting (No.)	0 (Test), 1(External Input Terminal 1), 2(External Input Terminal 2), 33(Interval Timer), 145(Volume Detection), 161(VOP Rule 1), 162(VOP Rule 2), 163(VOP Rule 3), 164(VOP Rule 4), 165(VOP Rule 5), 166(VOP Rule 6), 167(VOP Rule 7), 168(VOP Rule 8), 169(VOP Rule 9), 170(VOP Rule 10), 171(VOP Rule 11), 172(VOP Rule 12), 173(VOP Rule 13), 174(VOP Rule 14), 175(VOP Rule 15)
%N	Trigger of Shooting(Text String)	"External Device Name (alphanumeric characters)", "Moving Object Detection Area Name 1/2/3/4", "NULL (blank character/cases of interval timer and test)"
%X	Image Width	Number of pixels in the horizontal direction
%Y	Image Height	Number of pixels in the vertical direction
%C	Camera Number	1
%D	Camera Name	Setting value of "Camera Name (alphanumeric characters)"
%P	Pan Position	-179.99 – 180.00
%T	Tilt Position	-179.99 – 180.00
%Z	Zoom Position	0.01 – 300.00
%V	Camera Server	VB-M40/VB-M600/VB-M700
%y	Year of Shooting	2001 – 2031
%m	Month of Shooting	1 – 12
%d	Day of Shooting	1 – 31
%w	Day of week of Shooting	0 – 6 (correspond to Sunday to Saturday)
%H	Hour of Shooting	00 – 23
%M	Minute of Shooting	00 – 59
%S	Second of Shooting	00 – 59
%s	Millisecond of Shooting	000 – 999
%z	Time Zone of Shooting time	-1200 – +1300
%a	Day of Week Name of Shooting	Sun, Mon, Tue, Wed, Thu, Fri, Sat
%b	Month Name of Shooting	Jan, Feb, Mar, Apr, May, Jun, Jul, Aug, Sep, Oct, Nov, Dec
%h	Host Name	

## Message sent upon upload

An HTTP upload is transmitted as a GET or POST request.

Which type of request is used, a GET request or a POST request is determined based on the “Notification” setting.

A) When selecting “Notification Only with HTTP”

The following formatted message is transmitted.

```
GET {URI setting value}?{Parameter setting value } HTTP/1.1\r\n
```

```
...
```

```
User-Agent: Canon Network Camera VB/4.0\r\n
```

B) When selecting “Image attached Notification with HTTP”

The following formatted message is transmitted.

```
POST {URI setting value}?{ Parameter setting value } HTTP/1.1
```

```
...
```

```
User-Agent: Canon Network Camera VB/4.0\r\n
```

```
Content-Type: image/jpeg\r\n
```

```
Content-Length: {JPEG image data length}\r\n
```

```
\r\n
```

```
{JPEG data}
```

### [Note]

As a method of uploading file from the browser, <input type="file" ...> is generally used.

However, it should be noted that a method different from the above is used to upload JPEG images in VB-M40/VB-M600/VB-M700.

■ Notes when using major languages for CGI creation

C) CGI.pm package in perl

In the case of a jpeg image attachment, a URI parameter cannot be obtained with params() method. Instead, use url\_params() method.

A jpeg image included in the body of a POST request can be obtained with param('POSTDATA') .

Example:

```
use CGI;
...
my $query = new CGI;

my $jpeg = $query->param('POSTDATA'); # Obtain jpeg

open(JPG, ">", "sample.jpg") or die "error"; # Write to a file
binmode JPG;    # Specify binary mode for Windows
print JPG $jpeg;
close(JPG);
```

D) CGI library in ruby

In the case of a jpeg image attachment, when CGI objects are generated with CGI.new, image data may be destroyed. Do not generate CGI objects. Only use class method.

For example, when obtaining a URI parameter, it is possible to convert into hash with CGI.parse method as follows.

Example:

```
require 'cgi'
...
params = CGI.parse(ENV['QUERY_STRING'])
```

Read a jpeg image included in the body of a POST request from standard input.

Example:

```
$stdin.binmode          # Specify binary mode for Windows
jpeg = $stdin.read       # Read from standard input
f = open("sample.jpg", "w")
f.binmode
f.write(data)
f.close
```

E) cgi modules in python

In the case of a jpeg image attachment, when FieldStorage objects are generated with `cgi.FieldStorage()`, image data may be destroyed. Do not generate FieldStorage objects. Use functions such as `parse_qs`.

For example when obtaining a URI parameter, it is possible to convert into dictionary with `parse_qs` function as follows.

Example:

```
import os,cgi
params = cgi.parse_qs(os.environ['QUERY_STRING'])
```

Read a jpeg image included in the body of a POST request from standard input.

Example:

```
import os,sys,cgi
...
jpeg = sys.stdin.read      # Read from standard input
f = open("sample.jpg", "w")
f.write(data)
f.close()
```

\*Process in binary mode in Windows environment as follows.

```
import os,sys
...
if sys.platform == "win32":
    import msvcrt
    msvcrt.setmode(sys.stdin.fileno(), os.O_BINARY)
...
jpeg = sys.stdin.read
f = open("sample.jpg", "wb")
f.write(data)
f.close()
```



## G Each Command and User Access Privileges

The table below explains which access privilege is required to execute each command of the WV-HTTP protocol.

Legend: ○: Available

△: Conditionally available

×: Unavailable

Command Name	Guest Users	Authorized Users (Without Privileged Camera Control Authority)	Authorized Users (With Privileged Camera Control Authority)	Administrator Users.
open.cgi	△(Limited to priority=0)	△(Limited to priority=0)	○(Possible to specify priority=1 or more)	○(Possible to specify priority=1 or more)
close.cgi	○	○	○	○
claim.cgi	△ (Camera Control privilege is required.)	△ (Camera Control privilege is required.)	○	○
yield.cgi	○	○	○	○
session.cgi	△(Limited to priority=0)	△(Limited to priority=0)	○(Possible to specify priority=1 or more)	○(Possible to specify priority=1 or more)
image.cgi	△ (Image Distribution privilege is required.)	△ (Image Distribution privilege is required.))	○	○
video.cgi	△ (Image Distribution privilege is required.)	△ (Image Distribution privilege is required.))	○	○
info.cgi	○	○	○	○
panorama.cgi	○	○	○	○
control.cgi	△ (Camera Control privilege is required. Impossible to operate Day/Night switching mode and External output control. )	△(Camera Control privilege is required. Impossible to operate Day/Night switching mode and External output control. )	○	○